

US009245241B2

US 9,245,241 B2

Jan. 26, 2016

# (12) United States Patent Kite et al.

#### (54) METHODS, SYSTEMS AND COMPUTER PROGRAM PRODUCTS FOR PLANNING RESOURCES BASED ON PRIMARY AND ALTERNATE LOCATION RELIEF STRATEGIES

(75) Inventors: Joshua Kite, Atlanta, GA (US); Lynn B.

Horton, Atlanta, GA (US)

(73) Assignee: AT&T Intellectual Property I, L.P.,

Atlanta, GA (US)

(\*) Notice: Subject to any disclaimer, the term of this

patent is extended or adjusted under 35

U.S.C. 154(b) by 2837 days.

(21) Appl. No.: 10/885,191

(22) Filed: Jul. 6, 2004

(65) **Prior Publication Data** 

US 2005/0149372 A1 Jul. 7, 2005

#### Related U.S. Application Data

- (60) Provisional application No. 60/518,606, filed on Nov. 7, 2003.
- (51) **Int. Cl. G06Q 10/00** (2012.01) **G06Q 10/06** (2012.01)
- (52) U.S. Cl. CPC ........... *G06Q 10/06* (2013.01); *G06Q 10/06312*
- (2013.01); *G06Q 10/06315* (2013.01) (58) Field of Classification Search

### (56) References Cited

(10) Patent No.:(45) Date of Patent:

#### U.S. PATENT DOCUMENTS

6.040.774		4/2000	P 705/0		
6,049,774		4/2000	Roy 705/8		
6,681,231	B1*	1/2004	Burnett 707/104.1		
6,779,030	B1 *	8/2004	Dugan et al 709/223		
6,990,458	B2 *	1/2006	Harrison et al 705/8		
7,181,302	B2 *	2/2007	Bayne 700/96		
7,409,356	B1*	8/2008	Geddes et al 705/7.25		
8,311,865	B2*	11/2012	Vogel et al 705/7.12		
2002/0156917	A1*	10/2002	Nye 709/238		
2002/0194045	A1*	12/2002	Shay et al 705/8		
2002/0198898	A1*	12/2002	Werner 707/200		
2004/0008125	A1*	1/2004	Aratow et al 340/870.07		
2004/0174835	A1*	9/2004	Godwin et al 370/316		
OTHER PUBLICATIONS					

Bailey, "Problems with Using Overlay Mapping for Planning and Their Implications for Geographic Information Systems", Environmental Management, vol. 12, No. 1, pp. 11-17, 1988.\*


#### \* cited by examiner

Primary Examiner — Thomas L Mansfield, Jr. (74) Attorney, Agent, or Firm — Myers Bigel Sibley & Sajovec, PA

#### (57) ABSTRACT

In a computer-based method of planning resources, a plurality of Location Relief Strategy (LRS) plan data sets are imported into a resource planning application. The LRS plan data sets are associated with a resource need. One of the LRS plan data sets is defined as a primary LRS plan and at least one other one of the LRS plan data sets is defined as an alternate LRS plan. A resource plan is generated within the resource planning application based on the primary LRS plan and the alternate LRS plan. The primary LRS plan and the alternate LRS plan may each correspond to a plan for at least one of installing and retiring resources in a geographic area. The resources may, for example, be resources for carrying telecommunications in a geographic area.

#### 19 Claims, 18 Drawing Sheets






Figure 1




Figure 2




Figure 3




Figure 4




Figure 5




Figure 6




Figure 7





Figure 8



Location Relief Strategy

State Transition Diagram - Primary LRS




Figure 10

### Location Relief Strategy

State Transition Diagram -Alternate LRS




Figure 11




Figure 12




Figure 13




Figure 14




Figure 15




Figure 16







Figure 17




Resource Planning System 100

Figure 18










Figure 22

#### METHODS, SYSTEMS AND COMPUTER PROGRAM PRODUCTS FOR PLANNING RESOURCES BASED ON PRIMARY AND ALTERNATE LOCATION RELIEF STRATEGIES

#### RELATED APPLICATION

This application claims the benefit of and priority to U.S. Provisional Patent Application No. 60/518,606, filed Nov. 7, 2003, the disclosure of which is hereby incorporated herein by reference as if set forth in its entirety.

#### FIELD OF THE INVENTION

The present invention relates to computer systems and more particularly to methods, systems, and computer program products for computer based resource planning.

#### BACKGROUND OF THE INVENTION

Planning resources, such as telephone network resources, generally involves determining what resource needs are expected over time, and examining the resources that are presently available and/or that need to be installed to satisfy 25 the expected needs. Such planning once exclusively involved rendering resources that may be installed (i.e., planned resources) as mark-ups on transparent sheets, which were overlaid on paper geographic resource maps that included illustrations of existing resources. The transparent sheets and 30 paper geographic maps then formed a location relief strategy for how existing and planned resources could be used to satisfy a resource need. Digital representations of geographic maps have increasingly become available through, for example, Geographic Information System (GIS) tools. Some 35 GIS tools allow users to define and associate resources with geographic features of the digitized maps.

#### SUMMARY OF THE INVENTION

Some embodiments of the present invention provide computer-based methods of planning resources based on a resource need. A plurality of Location Relief Strategy (LRS) plan data sets are imported into a resource planning application. The LRS plan data sets are associated with a resource 45 need. One of the LRS plan data sets is defined as a primary LRS plan and at least one other one of the LRS plan data sets is defined as an alternate LRS plan. A resource plan is generated within the resource planning application based on the primary LRS plan and/or the alternate LRS plan.

In some further embodiments of the present invention, the LRS plan data sets can be prioritized. The highest priority LRS plan data set can be selected as the primary LRS plan, and at least one other of the LRS plan data sets can be designated as the alternate LRS plan (s). The primary LRS plan may be changed to be an alternate LRS plan, and the alternate LRS plan may be changed to be a primary LRS plan. The primary LRS plan and/or the alternate LRS plan may be selectively displayed based on selections from a user. A plurality of LRS plan data sets may be associated with a plurality of resource needs, with one of the LRS plan data sets for each of the plurality of resource needs being defined as a primary LRS plan the primary LRS plan data sets for each of the plurality of resource needs being defined as a primary LRS plan that sets for each of the plurality of resource plan for each of the resource needs may be generated, and may be displayed to a user.

In some other embodiments of the present invention, the 65 primary LRS plan and the alternate LRS plan may each correspond to a plan for installing and/or retiring resources in a

2

geographic area. The resources may include resources for carrying telecommunications in a geographic area. A LRS plan may include, for example, a plan for installing a number of fiber optic communication lines and/or electrical communication lines at a geographic location.

Accordingly, more than one LRS plan may be associated with a resource need. When more than one LRS plan is associated with a resource need, one of the plans may be defined as a primary LRS plan and the other plan(s) may be defined as alternate LRS plan(s). The primary LRS plan may correspond to what a Long Term Planner perceives as a preferred way of satisfying the associated resource need, while the alternate LRS plans may correspond to what are perceived as less preferred ways. Such association of a preferred LRS plan and alternate LRS plans with a resource need may allow a Long Term Planner to define many different resource plans for meeting a resource need, and to designate a preferred resource plan while maintaining the other LRS plans for further use (e.g., documentation and/or analysis).

Other systems, methods, and/or computer program products according to embodiments will be or become apparent to one with skill in the art upon review of the following drawings and detailed description. It is intended that all such additional systems, methods, and/or computer program products be included within this description, be within the scope of the present invention, and be protected by the accompanying claims.

#### BRIEF DESCRIPTION OF THE DRAWINGS

FIG. 1 is a high-level view of the responsibilities of the exemplary user groups that may use a Fiber Management Tool (FMT) according to embodiments of the present invention.

FIG. 2 depicts a block diagram of the FMT.

FIG. 3 depicts a comparison between the "new" and "existing" objects in a FAS database.

FIG. 4 is a graphical view of a nine state region level provided by an exemplary FMT.

FIG. 5 is a graphical view of the multi-state region level provided by an exemplary FMT.

FIG. 6 is a graphical view of the wire center level provided by an exemplary FMT.

FIG. 7 is a high-level graphical view of the street level provided by an exemplary FMT.

FIG.  $\bf 8$  is a low-level graphical view of the street level provided by an exemplary FMT.

FIG. 9 depicts the relationships between exemplary components in a Location Relief Strategy (LRS).

FIG. 10 is a state transition diagram that depicts the functions of a LRS within a FMT.

FIG. 11 is a state transition diagram that depicts functions of an alternate LRS within a FMT.

FIG. 12 depicts an exemplary display of a returned data window and data discrepancies.

FIG. 13 depicts an exemplary systems development life cycle methodology followed for internally developed systems and major enhancements.

FIG. 14 depicts an exemplary three-tier architecture of an OPEDS system.

FIG. 15 depicts an OPEDS topology.

FIG. 16 depicts an OPEDS data center.

FIG. 17 depicts a typical district/RLAC.

FIG. 18 is a block diagram of a resource planning system suitable for use in embodiments of the present invention.

FIG. 19 depicts an exemplary display of existing resources and resource needs.

3

FIG. 20 depicts an exemplary resource plan that displays primary LRS plans and alternate LRS plans responsive to the resource needs shown in FIG. 2.

FIG. 21 depicts an exemplary resource plan that displays only primary LRS plans responsive to the resource needs 5 shown in FIG. 2.

FIG. 22 is a flowchart illustrating operations for planning resources based one or more resource needs according to various embodiments of the present invention.

#### DETAILED DESCRIPTION

The present invention now will be described more fully hereinafter with reference to the accompanying drawings, in which illustrative embodiments of the invention are shown. 15 This invention may, however, be embodied in many different forms and should not be construed as limited to the embodiments set forth herein; rather, these embodiments are provided so that this disclosure will be thorough and complete, and will fully convey the scope of the invention to those 20 skilled in the art. Like numbers refer to like elements through-

The detailed description of embodiments of the present

invention is organized as follows: 1 Overview 25 2 Introduction 3 Description of Users and Information Needs 3.1 Local Planners (Facility Planners) 3.2 Long-Term Planners 3.3 Infrastructure Inter-Office (IOF) Planners 3.4 Construction 4 Baseline Systems and Data 5 Diagrams 5.1 High Level Relationship 5.2 Comparison of Systems

6 Client Application Layer 6.1 Login/Password 6.2 Graphical and Tabular Fiber Capabilities

6.2.1 Search/Find, View Graphical Elements 6.2.1.1 Provide Views and Functions in a Seamless Envi- 40 ronment

6.2.1.2 Provide Default Views 6.2.1.3 Specify Scaling Capability 6.2.1.4 Specify Search Criteria

6.2.1.5 Provide Additional Search Functions

6.2.1.6 Format Query Results

6.2.1.7 Display Multiple Query Results 6.2.1.8 Define Default Views

6.2.1.8.1 Default View by User Type

6.2.1.8.2 Nine State Region

6.2.1.8.3 Multi State 6.2.1.8.4 Single State

6.2.1.8.5 District

6.2.1.8.6 Wire Center

6.2.8.1.7 Street Level

6.2.2 Select and Query Visible Graphical and Network Facility Items

6.2.2.1 List Attributes of a Fiber Sheath

6.2.2.2 List Attributes of a Fiber Splice

6.2.2.3 List Attributes of a Fiber Strand

6.2.2.4 List Attributes of an Equipment Location

6.2.2.5 Display Data Attributes of a Conduit

6.2.2.6 Display Data Attributes of Landbase Features

6.2.3 Provide Fiber Calculation Tools

6.2.3.1 Determine Number of Splices in a Strand

6.2.3.2 Provide Distance Between Points on a Fiber Strand

6.2.3.3 Provide Distance Between Geographic Points

4

6.2.3.4 Calculate and Display Anticipated dB Loss of Fiber Strand Path

6.2.3.5 Input Loss and Locate Fiber Cut

6.2.3.6 Generate Restoration Order Based On System/User

6.2.4 Generate Fiber Schematics

6.2.4.1 Use Automatic Schematics Tool

6.2.4.2 Use Manual Schematics Tool

6.2.5 Integrate Fiber Related Data

6.2.5.1 Add Fiber Strand and Derived Wavelength Data

6.2.5.2 Provide Connectivity Between Fiber Strand and Equipment Slot

6.2.5.3 Provide SCID Relationships to Fiber Strand and Equipment Slot

6.2.5.4 Provide LEAD and TIRKS Circuit IDs

6.2.5.5 Capture Fiber Diversity Information

6.2.5.6 Capture Fiber Connections from FOX

6.2.5.7 Capture a LOC/CLLI and Address from LOC/ CLLI System

6.2.5.8 Capture Easement/ROW Information for Locations from BETS

6.2.5.9 Generate Land Base For Non-OPEDS Converted Wire Centers

6.2.5.10 Develop Mechanized Processes From Legacy System Sources

6.2.5.11 Manage Out of Franchise Fiber and Equipment

6.2.5.12 Display and Identify CLEC Sheaths and Equipment

6.2.5.13 Allow Entry of Fiber Loss Data

6.2.5.13.1 Allow Manual Entry of Fiber Loss Data

6.2.5.13.2 Allow Automatic Entry of Fiber Loss Data

6.2.5.14 Display Measured Loss

6.2.6 Provide Fibers and Related Equipment Search and

6.2.6.1 Display Cabinets for Specified Equipment Loca-

6.2.6.2 Display Devices for Selected Structure—Filter by

6.2.6.3 Display Selected Device Attributes

6.2.6.4 Display Device Slots and Related Circuits

6.2.6.5 Locate Equipment by Address

6.2.7 Provide Fibers and Equipment Utilization Monitor-

6.2.7.1 Provide CSA Utilization by Service Type

6.2.7.2 Provide CSA Alerts to FACILITY PLANNERS

6.2.7.3 Determine Fiber Strand Utilization

6.2.7.3.1 Determine Whether Physical Strand is Assigned

6.2.7.3.2 Determine Physical and Derived Fiber Strand Utilization

6.2.7.3.3 Determine Carrier Signal Level Utilization for a Strand

6.2.7.3.4 Determine DS0 Equivalent Utilization for Virtual and Physical Fiber Strands

6.2.7.4 Determine Fiber Sheath Utilization

6.2.7.5 Determine Utilization Trend Analysis

6.2.7.6 Determine Fiber Cross-Section Alerts

6.2.7.7 Determine MUX Utilization

6.2.7.8 Monitoring Point

50

6.2.7.9 Xbox and CSA History and Trending

6.2.8 Provide Fiber Tools and Reports

6.2.8.1 Generate Equipment Site Activity Log

6.2.8.2 Allow User to Determine Fiber Strand Diversity

6.2.8.3 Assign Restoration Priority for a System Assembly

6.2.8.4 Assign Reservation for a Fiber Strand

6.2.8.5 Provide Numbering Administration Tools

6.2.8.5.1 Add System Numbering Tool

6.2.8.5.2 Add SCID Administration Tool

6.2.8.6 Enhance Existing Database, Posting & Viewing **7.1.5 TIRKS** 6.2.8.7 Develop Tools to Populate the Facility Data 7.1.6 LEIM Enhancements 7.1.7 BCM 6.2.8.8 Develop Tools to Add Existing Fiber and CSA 5 7.1.8 PM TOOLLocations 6.2.8.9 Allow User To Perform Fiber Traces **7.1.9 TEOPS** 6.3 Planning Layer Functionality 6.3.1 LRS Overview 6.3.1.1 LRS States 8.2 LRS Search 10 6.3.1.2 Primary LRS State Transitions 6.3.1.3 Alternate LRS 6.3.1.4 Alternate LRS State Transitions 8.5 MUX 6.3.2 Provide Location Relief Strategy Administration 8.6 DSX 8.7 LGX 6.3.2.1 Create a LRS and Associated Administrative Data 8.8 ONU 6.3.2.2 Create Alternative LRS and Associate for a Route 8.9 NMLI 6.3.2.3 Modify LRS Administrative Data 8.10 DLC 6.3.2.4 Save and Retrieve LRS and Administrative Data 8.11 Fiber Splice 6.3.2.5 Logically Delete LRS and Associated Data 8.12 Switch 20 6.3.2.6 Purge LRS and Associated Data 6.3.2.7 Create, Modify, and Delete LRS Notes by User 8.14 Fiber Strand 6.3.2.8 Provide LRS Reports by User Selection Filters 8.15 Fiber Sheath 6.3.2.9 Close a LRS Manually 6.3.2.10 Alert Overage Service Dates on LRS 8.17 Conduit 6.3.2.11 Dependent LRS Clone 6.3.3 Provide Graphical and Tabular Planning Tools 6.3.3.1 Generate LRS Schematics From Existing Fiber Data 6.3.3.2 Provide Drawing Tools, Symbols, and Attribute 30 9.1.1.2 Actors Creation Functions 6.3.3.3 Document Future Location Relief Strategy, and/or **DLE Locations** 6.3.3.4 Retrieve and Display LRS 6.3.3.5 Display Multiple LRS Graphically 35 9.2.2.2 Actors 6.3.3.6 Copy Existing LRS to New LRS 6.3.3.7 Modify LRS 6.3.3.8 Publish LRS 6.3.3.9 View LRS and DLE Plans 6.3.3.10 View Multiple LRS for Same Geographic Area 9.2.3.2 Actors 6.3.3.11 Capture LRS Notes Associated with a Graphical Feature by User 6.3.3.12 Manage Graphical Feature LRS Notes by User 6.3.3.13 Link to Tabular LRS Data at Location Features 6.3.3.14 Measure Strand Distances 9.2.4.2 Actors 6.3.3.15 Provide View Printing 6.3.3.16 Create an Equipment Plan Associated to a LRS and Location 6.3.3.17 Create Fiber Strand Plans Associated to LRS and Sheath 9.2.5.2 Actors 50 6.3.3.18 Provide Summary Reports 6.3.3.19 Create Ad Hoc Monitoring Queries and Reports 6.3.3.20 LRS Handoff Package 6.3.3.21 Monitor Facility and Fills 6.3.3.22 Provide Inventory Tasks on Equipment/Site 55 9.2.6.2 Actors Details 6.3.3.23 Maintain Editing History 6.3.3.24 Create "Publish" Pop-Up Window 6.4 Exit, Session, Recovery, and Cleanup 6.5 Performance 9.2.7.2 Actors 60 6 External System 7.1 External Systems Communications 7.1.1 LECIII 7.1.1.1 LEC III Data Embodiments 9.2.8.1 Description 7.1.2 LOC/CLLI 9.2.8.2 Actors

**7.1.3 LFACS** 

7.1.4 FOX/DSX/TEOPS

6 7.1.4.1 FOX/DSX Data Embodiments 7.1.8.1 PM Tool Data Embodiments 7 Data Embodiments 8.1 LRS & Hand-Off Package 8.3 Facility Route Search 8.4 Equipment Attributes 8.13 Repeater Shelf 8.16 Equipment Location 9 Use Case Modeling 9.1 Use Case Descriptions 9.1.1 Use Case: Login and Password 9.1.1.1 Description 9.1.1.3 Normal Sequence 9.1.1.4 Alternative Sequence 9.2.2 Use Case: Search/Find, View Graphical Elements 9.2.2.1 Description 9.2.2.3 Normal Sequence 9.2.2.4 Alternate Sequences 9.2.3 Use Case: Query Network Facility Items 9.2.3.1 Description 9.2.3.3 Normal Sequence 9.2.3.4 Alternative Sequence 9.2.4 Use Case: Provide Calculation Tools 9.2.4.1 Description 9.2.4.3 Normal Sequence 9.2.4.4 Alternative Sequence 9.2.5 Use Case: Integrate Fiber Related Data 9.2.5.1 Description 9.2.5.3 Normal Sequence 9.2.5.4 Alternative Sequence 9.2.6 Use Case: Provide Fiber Tools and Reports 9.2.6.1 Description 9.2.6.3 Normal Sequence 9.2.6.4 Alternative Sequence 9.2.7 Use Case: Create, Read, Update, Delete LRS 9.2.7.1 Description 9.2.7.3 Normal Sequence 9.2.7.4 Alternate Sequences 9.2.8 Use Case: View Cross Box Data for Planning

9.2.8.3 Normal Sequence

9.2.8.4 Alternative Sequence

10 Technical

10.1 General

10.2 Computing Architecture

10.3 Computer Asset Protection Guidelines

10.4 SDLC

10.5 Other Standards And Guides

10.5.1 GUI Style Guide

10.5.2 Capability Maturity Model

10.5.3 Metrics

10.5.4 Configuration Management

10.6 Technical Design

10.6.1 Design

10.6.2 Open Systems

10.6.3 Open APIs

10.6.4 Interfaces

10.6.5 PC Client Data Access

10.6.6 Portability

10.6.7 Software Development Tools

10.6.8 Naming Conventions

10.6.9 Information Modeling

10.6.10 Data

10.6.11 Data Movement

10.6.12 User Interface Design

10.6.13 On-line Help

10.6.14 Security Embodiments

10.6.15 User Identification

10.6.16 Security Audit

10.6.17 Operations

10.6.18 Backup and Recovery

10.6.19 Application Management

10.6.20 Error Resolution

10.6.20.1 Client Application/User Errors

10.6.20.2 Technical Errors

10.6.21 Timing Embodiments

10.6.22 Load Projections

10.6.23 Software Delivery

10.6.24 Work Center Application Integration Group

10.7 Current OPEDS Architecture

10.7.1 Overview

10.7.1.1 External System Data

10.7.1.2 OPEDS

10.7.2 Workstation Specifications

10.7.3 Server/Database Specifications

10.7.4 System Diagram

10.8 Computing Architecture

10.8.1 OPEDS Data Repositories

10.8.1.1 Landbase

10.8.1.2 Facilities

10.8.2 Network Information Services

10.8.3 Domain Name System (DNS)

10.8.4 OPEDS Process/Data Management Layer

10.8.5 Wide Area Network

10.8.6 External System Data

10.9 OPEDS Topology

10.9.1 Data Center

10.9.2 Typical District/RLAC

11 Reference Items

11.1 Glossary of Terms for the FMT and Systems

12 Further Details With Respect to Methods, Systems and Computer Program Products for Planning Resources <sub>65</sub> Based on Primary and Alternate Location Relief Strategies 8

1 Overview

As will be appreciated by one of skill in the art, the present invention may be embodied as a method, data processing system, or computer program product. Accordingly, the present invention may take the form of entirely software embodiments or embodiments combining software and hardware aspects. Furthermore, the present invention may take the form of a computer program product on a computer-usable storage medium having computer-usable program code embodied in the medium. Any suitable computer readable medium may be utilized including hard disks, CD-ROMs, optical storage devices, a transmission media such as those supporting the Internet or an intranet, or magnetic storage

Computer program code for carrying out operations of the present invention may be implemented using programmable aspects of existing application programs such as, for example, 20 application programs that may interface to, or be at least partially integrated with, Geographical Information System (GIS) tools and/or databases that can store geographic and resource information. Aspects of the computer program code may also be written in an object oriented programming language such as Java®, Smalltalk or C++ and/or using a conventional procedural programming languages, such as the "C" programming language. The program code may execute entirely on the user's computer, partly on the user's computer, as a stand-alone software package, partly on the user's computer and partly on a remote computer or entirely on the remote computer. In the latter scenario, the remote computer may be connected to the user's computer through a local area network (LAN) or a wide area network (WAN), or the con-35 nection may be made to an external computer (for example, through the Internet using an Internet Service Provider).

The present invention is described below with reference to flowchart illustrations and/or block diagrams of methods, apparatus (systems) and computer program products according to embodiments of the invention. It will be understood that blocks of the flowchart illustrations and/or block diagrams, and combinations of blocks in the flowchart illustrations and/or block diagrams, can be implemented by com-45 puter program instructions. These computer program instructions may be provided to a processor of a general purpose computer, special purpose computer, or other programmable data processing apparatus to produce a machine, such that the instructions, which execute via the processor of the computer or other programmable data processing apparatus, create means for implementing the functions/acts specified in the flowchart and/or block diagram block or blocks.

These computer program instructions may also be stored in a computer-readable memory that can direct a computer or other programmable data processing apparatus to function in a particular manner, such that the instructions stored in the computer-readable memory produce an article of manufacture including instruction means which implement the function/act specified in the flowchart and/or block diagram block or blocks.

The computer program instructions may also be loaded onto a computer or other programmable data processing apparatus to cause a series of operational steps to be performed on the computer or other programmable apparatus to

produce a computer implemented process such that the instructions which execute on the computer or other programmable apparatus provide steps for implementing the functions/acts specified in the flowchart and/or block diagram block or blocks.

Various embodiments of the present invention provide computer-based resource planning using a resource planning application. For purposes of illustration only, some of these embodiments are described herein in the context of planning communication resources, such as fiber optic communication lines and/or electrical communication lines. In particular, some embodiments of the present invention are described with regard to a Fiber Management Tool (FMT). It will be understood, however, that the present invention is not limited to planning of communication resources. Indeed, other resources, such as, but not limited to, gas lines, water lines, electrical lines, and/or television lines may be planned by other embodiments of the present invention. In general, the 20 present invention is intended to encompass any technology and/or configuration capable of carrying out the operations described herein.

#### 2 Introduction

Resource planning systems, methods and computer pro- 25 gram products according to some embodiments of the invention, referred to herein, may be embodied in a Fiber Management Tool (FMT). The FMT can be a computer-based application that may provide an integrated view and monitoring of utilization of an existing fiber optic network and associated digital loop electronics, and may make this information more readily accessible to Network FACILITY PLAN-NERSs, Designers, Long Term Planners, and Construction Repair technicians, which may shorten information research time. The FMT may use land, facility, and equipment data stores. The FMT may run as an application on one or more servers, such as HP Unix servers that include Oracle for managing database attributes, and may include a DGN format for graphical files. The FMT application may display a graphical as well as a tabular view of data. The graphical layer may graphically display fiber network elements (ex. Fiber routes, remote terminals, central offices, equipment), supporting structures (ex. Conduit, manholes, poles) at defined 45 geographical levels (ex. Wire center, state, district), and/or associated landbase features (ex. Streets, parcels, lakes, riv-

The FMT may include the functionality of, or integrate with, existing Mechanized Facility Management databases, posting tools, and viewing tools to support additional fiber functionality: Inter-wire center connector, fiber splice feature, graphical location of fiber in Underground records, and CSA/Equipment Location feature. It may provide a development tools to automatically populate the facility data enhancements. The FMT may include tools to add existing fiber and CSA locations, along with key structure and connectivity features/attributes to the FMT SDO Database; both automatically from mechanized wire centers, and manually for non-mechanized wire centers. In addition to the IOF and feeder fiber network, FMT can also include distribution fiber.

The FMT may include a central repository for documenting Location Relief Strategies (LRS) plans created by 65 FACILITY PLANNERSs and Long Term Planners. The FMT may include a planned data layer that allows definition of

10

FACILITY PLANNERS, and tool for creating and maintaining future LRSs including fiber network, fiber strands, and associated DLE information. The FMT may include create a planning schematic from the existing network data, and may allow an automated "hand-off" of a selected LRS to a PM Tool system for the design process. Searches may be performed for primary and/or alternate LRSs.

The FMT may generate a land base for non-OPEDS converted wire centers with the location of central offices, equipment sites and x-boxes from the existing OPEDS land base data. It may provide mechanized processes and rules to load data and manage data conflicts from separate legacy system sources and user input from local records, and determine appropriate source to use to provide existing fiber and equipment attributes.

Potential users of the system and their basic needs are now described below, followed by a detailed discussion of various embodiments of the invention. The subsequent sections discuss the various embodiments in further detail and provide information about data, relationships, applicable business rules, and standards.

3 Description of Users and Information Needs

Purpose: The following section describes the various user groups that FMT can serve. Each section gives a brief overview of each user group's responsibility and their information needs.

Discussion: FMT's target users comprise of four groups. These groups are:

Local Planners (FACILITY PLANNERSs)

Infrastructure Loop Planners

Infrastructure Inter-Office (IOF) Planners

Construction

FIG. 1 provides a high-level view of the major user group's responsibilities.

3.1 Local Planners (Facility Planners)

FACILITY PLANNERS often answer requests for information from Marketing, Long Term Planners, and Inter-Office Planners. Local Planners have access to several sources of data. These include OPEDS Facility Database (Map-Viewer), LEIM, TIRKS, LFACS, and personal records, which makes them a de facto data repository for almost all of a telecommunication company's fiber optic assets. FMT can aggregate the information supplied by these external systems, providing Local Planners with a synchronized, consistent view of the data.

3.2 Long Term Planners

This group is responsible for high-level business planning, and analyzing metro-area and surrounding infrastructure. This group maintains information in personal records, stored primarily in spreadsheets (Microsoft Excel) and local databases (Microsoft Access). Long Term Planners provide Marketing with information. They also share information with Local Planning and Inter-Office Planners. Often, Long Term Planners require additional information, and personnel must contact Local Planning or Inter-Office Planners. FMT can provide Long Term Planners with timely information and eliminate the need for them to contact the other groups directly.

#### 3.3 Infrastructure Inter-Office (IOF) Planners

Inter-Office Planners are responsible for designing the architecture for closed system, fiber-optic networks for busi-

nesses. A significant amount of their work revolves around the provisioning of advanced telephony services. Inter-Office Planners often rely on Long Term Planners and Local Planners to fulfill their information needs. Inter-Office Planners desire fiber route records, but have may only high-level schematics and assignment data. They often coordinate with Local Planners to make ring-routing decisions. FMT can provide Inter-Office Planners with fiber routing information and detailed schematics and streamline their interaction with 10 other planning groups.

#### 3.4 Construction

The Construction group has little direct involvement with managing fiber optic assets and is not involved in the information flow among the other groups. However, Construction is responsible for repair and splicing work. The Splicing Technicians in Construction deal with major problems (a cut cable) and minor problems (a missing jumper in a Light Cross Connect (LGX). Splicing Technicians currently have the ability to determine fault distances using an Optical Time Domain Reflectometer (OTDR). FMT can help them complete the "picture" of the problem by correlating this OTDR distance data with a geographic location. With geographic data available, Splicing Technicians can resolve problems more quickly.

#### 4 Baseline Systems and Data

For the purpose of developing/implementing Fiber Management Tool, the following systems and data sets are <sup>30</sup> assumed to exist:

#### Landbase

A landbase is a representation of streets, rights of ways, and various boundaries. This data may be stored in an Oracle database utilizing GIS software such as that provided by ESRI.

#### Facility

A mechanized facility database is a representation of the various facilities which comprise the telephone network. 40 Facilities represented include, but are not limited to, poles, manholes, copper cables, terminals, and fiber cables. This graphical representation may be stored in a GIS database or in graphics files such as .dgn files.

#### Land & Facility Data Exchange

A Land and Facility Exchange is a means of synchronizing the two data stores to ensure that the facilities represented are shown in proper relation to the streets and rights of ways.

#### Equipment Database

The Equipment Database reconciles records of telephone equipment and assignment records from various databases. The reconciled records may be from systems such as LEIM, LFACS, and TIRKS.

#### 5 Diagrams

#### 5.1 High Level Relationship

In the development and design of Fiber Management System, a goal is to add new fiber information to existing by extracting data from various External Systems and Facility Management to display information in FAS via a Web interface. FIG. 2 represents the high level relationships for FMT.

#### 5.2 Comparison of Systems

Currently in FAS through the FAS umbrella, the "existing" as shown in FIG. 3, refers to the objects maintained in the FAS database. Within the existing objects, new data may be added. The objects depicted in FIG. 3 as "new" refer to the new

12

objects to be incorporated i.e. (Fiber Sheath, Fiber Connect Fiber Strand and Plan) in the FAS database. A Location Relief Strategy (LRS) is a mechanism that is used to record future network relief strategies, providing the user with the ability to document network modifications, document the justification, and communicate this information electronically to downstream users, i.e. design engineering vendors and external systems. The LRS may be developed for immediate or future relief. Within the existing information base, the user can monitor cross-box fills, equipment, site, slot, wire center and their capacities. With the new proposed FAS functionality the user can be able to drill down to the fiber strand information and link to the existing information base and view graphically via the Fiber Management Tool.

#### 6 Client Application Layer

Purpose: This section provides detailed information on FMT's application-layer embodiments, including functional-20 ity and expected behavior. The groupings are summarized in Table 1.

#### TABLE 1

Embodiment Grou	pings and Descriptions
Embodiment Groupings	Description
Login/Password	Describes a high-level architecture for login and password functions and user accessibility options.
Graphical and Tabular Fiber Capabilities	These embodiments describe the method for querying on specific criteria.  They also indicate the functionality and types of data that FMT can provide to a user in a graphical or text format.  Reporting are also included.
Planning Layer Functionality (LRS)	These embodiments indicate the functionality and types of data that FMT can provide for a user to plan future fiber network construction.
Utilize Data Supplied by External Systems	A brief summary of the functionality expected from FMT when reading data received from external systems.
Exit, Sessions, Recovery, and Cleanup	Summaries of the client interaction with the system as these functionalities are performed.
Performance Embodiments	These embodiments describe standard performance measures met by the system.

#### 6.1 Login/Password

55

Users may be granted access to FMT via a unique combination of user identification (CUID, Common User ID) and password. FMT can maintain user permissions—including access to the planning layer access permissions on default views, etc.—in a user table stored in a database on a secure server. This table can provide administrators with the flexibility to organize users and associated permissions into logical groups.

#### 6.2 Graphical and Tabular Fiber Capabilities

These embodiments indicate functionality needed to access information in FMT and manage the information pro-

different, FMT can indicate

13

Magnification Factor (e.g.,

cess. It also describes core functionality that FMT can pro--continued 6.2.1 Search/Find, View Graphical Elements zoom-in or zoom-out from a centered point on 6.2.1.1 Provide Views and Functions in a Seamless Envithe screen) ronment Select default views by indicating appropriate attributes (e.g., user selects Wire Center view and Embodiment Provide accurate graphical specifies a Wire Center views of geographical or user can select multifeatures and network 10 wire center view; user facilities in a seamless selects Street view by environment. indicating Wire Center Graphical views and fiber Description and street intersection) strand connectivity shall be Defining the Area of maintained across wire Interest by drawing a polygon center, district, state, and (e.g., user draws a polygon 15 other boundary types. at a Wire Center view, or multi-wire center view, and FMT shows a street 6.2.1.2 Provide Default Views level view the specified area) 20 Embodiment Provide support for default 6.2.1.4 Specify Search Criteria views containing a defined set of fiber network elements (facilities) and Embodiment Provide the user with the geographical features ability to select specific (landbase) based upon the type 25 parameters for querying of view presented. data. Description The GUI interface can provide Description The parameters can provide other geographical and fiber network elements that can be the user with the ability to define the scope of the query shown based upon a user's from a broad search (e.g., all request (i.e. turn features 30 equipment at a Central Office on or off). At a minimum, FMT can provide (CO)) to a more precise Data search (e.g., a specific item the following default views: of equipment at a CO). Nine State Region View Multi-State View State View District View 6.2.1.5 Provide Additional Search Functions Wire Center View Street View Embodiment Provide the user with the ability to further refine a 6.2.1.3 Specify Scaling Capability query by utilizing Boolean 40 searches. Description Users can base the searches Embodiment Ability to define the scale on an item or group of items of display and the ability to against a value or range of override the default scale values (e.g., all sheaths greater assigned to a default view. than 10000 feet). This function-45 Description As the scale of the view changes, ality is available for all data the level of detail for land entities and attributes. In and facility elements, as noted addition, the system can provide via symbology, can also the user with the ability to query on wildcards (e.g., "\*", change in a corresponding manner. Views and network "%"), in each data entry symbology can map to current 50 field to broaden or narrow the OPEDS, .LND, landbase, results of the search. For and .DGN in the facilities example, a user may want to find models previously described. all roads that start with "Peach", entering "Peach%" When the user changes the scale, FMT can toggle between in the query field. default views (e.g., if the 55 user is at the Nine-State view and changes the scale by zooming 6.2.1.6 Format Query Results in, FMT can, at a defined scale point, switch to the Multi-State view). Data FMT can provide the user with Embodiment Provide the user with the 60 the ability to specify the ability to further view the view and scale via the results of a query in both following manners: a graphical and/or tabular Map to Ground Ratio (e.g., 1:100) format. Map Unit equals Ground If a set of required data is Description Distance (e.g., 1 inch to 1 maintained in multiple external 65 mile, or 1 kilometer) systems and their values are

## 16 TABLE 2-continued

#### -continued

the source and values of each conflicting data set.			Behavior	Indicates the selection method (passover or click) that a user can perform to access information
6.2.1.7 Display Multiple Query Results		5	Attributes Displayed	about the object Indicates the data attributes that FMT can display if the object is selected
Embodiment	Allow the user with the ability to display multiple query results.	10	Default View	(Y = Yes) Indicates that FMT can automatically display the object in the default view (N = No) Indicates that FMT
Description	For example, a user may perform a loop trace on a fiber strand, then to perform a second one - while maintaining the original loop trace on screen - in order to compare the results.	15	Additional Information	can not automatically display the object in the default view, but is available at a user's request (e.g., user may turn object on or off) Provides information unique to the object

#### 6.2.1.8 Define Default Views

Embodiment	Show a defined set of land
	features and network
	facilities for each default
	view.
Description	Many of these items may be
	selectable by the user to view
	information and initiate a
	data query.

Table 2 indicates the format of the information provided for each default view.

#### 6.2.1.8.1 Default View by User Type

FMT can provide the administrative ability to associate a user with a specific role type and geographic area. Examples of role types include, but are not limited to, Facility Planners, InterOffice Planners, etc. Examples of geographical areas include, but are not limited to, State, District and Wire Center. Based on users' defaults, FMT can provide default functionality and graphical views.

#### 6.2.1.8.2 Nine State Region

FMT can provide a default view of a Nine-State region, which includes Alabama, Florida, Georgia, Kentucky, Louisiana, Mississippi, North Carolina, South Carolina, and Tennessee. Other regions may be provided. FIG. 4 suggests this concept.

Objects	Behavior	Attributes Displayed	Default View	Additional Information
		Land		
State Boundaries	N/A	N/A	Y	
State Names (Abbreviation)	N/A	N/A	Y	
District Boundaries	Passover District Area	District Name	Y	
Major Cities	N/A	N/A	Y	
Interstate Highways, with designation #	N/A	N/A	N	
Other Territory	N/A	N/A Facilities	N	
Fiber Routes (IOF only)	Click	Fiber Sheath Attributes of first sheath	N	Shown as a result of a query
Fiber Strands (IOF and Loop)	Passover	Fiber Strand Name	N	Shown as a result of a query
	Click	Fiber Strand Attributes		
Central Office Locations	Passover	Central Office Name	N	
	Click	Central Office Attributes		
Central Office Names	N/A	N/A	N	If Central Office Name is displayed, Central Office Location passover feature is disabled

#### TABLE 2

#### 6.2.1.8.3 Multi State

Indicates the network facility items that FMT can display at the default view FMT can provide a default multi-state view comprising an originating state and all the states that border the originating state. FIG. 5 suggests this concept.

Objects	Behavio	Attributes Displayed	Default View	Additional Information
		Land		
State Boundaries	N/A	N/A	Y	
State Names (Abbreviation)	N/A	N/A	Y	
District Boundaries	Passover District Area	District Name	Y	
Interstate Highways, with designation #	N/A	N/A	Y	
State Highways, with designation #	N/A	N/A	Y	
Major Cities	N/A	N/A	Y	
Other territory	N/A	N/A	Y	
Numbered Planning Area (NPA)	Click	NPA#	N	
(MA)		Facilities		
Fiber Routes (IOF only)	Click	Fiber Sheath Attributes of first sheath	N	Shown as a result of a query
Fiber Strands (IOF and Loop)	Passover	Fiber Strand Name	N	Shown as a result of a query
	Click	Fiber Strand Attributes		
Central Office Locations	Passover	Central Office Name	N	
	Click	Central Office Attributes		
Central Office Names	N/A	N/A	N	If Central Office Name is displayed, Central Office Location passover feature is disabled

6.2.1.8.4 Single State
FMT can provide a default single state view comprising a single state and partial boundaries of adjacent states. FIG. 5 illustrates the concept.

Objects	Behavior	Attributes Displayed	Default View	Additional Information				
Land								
State Boundaries	N/A	N/A	Y					
State Names (Abbreviation)	N/A	N/A	Y					
District Boundaries	N/A	N/A	Y					
District Names	N/A	N/A	Y					
Interstate Highways, with designation #	N/A	N/A	Y					
State Highways, with designation #	N/A	N/A	Y					
Major Cities	N/A	N/A	Y					
Water Bodies	Passover	Water Body Name	Y					
Other territory	N/A	N/A	Y					
County Boundaries	Click	County Name	N					
County Names	N/A	N/A	N	If County Name is displayed, County Boundary click feature is disabled				
Numbered Planning Area (NPA)	Click	NPA#	N					
Exchange	Click	Exchange #	N					
Local Access Toll Area (LATA)	Click	LATA#	N					

-continued

Objects	Behavior	Attributes Displayed	Default View	Additional Information
Airports	N/A	N/A	N	
Landmarks	N/A	N/A Facilities	N	
Fiber Routes (IOF only)	Click	Fiber Sheath Attributes of first sheath	Y	
Fiber Strands (IOF and Loop)	Passover Click	Fiber Strand Name Fiber Strand Attributes	N	Shown as a result of a query
Central Office Locations	Passover Click	Central Office Name Central Office Attributes	N	
Central Office Names	N/A	N/A	N	If Central Office Name is displayed, Central Office Location passover feature is disabled

6.2.1.8.5 District FMT can provide a default District view comprising the District and partial boundaries of adjacent Districts. FIG. 5 illustrates the concept.

Objects	Behavior	Attributes Displayed	Default View	Additional Information
		Land		-
State Boundaries	N/A	N/A	Y	
State Names (Abbreviation)	N/A	N/A	Y	
District Boundaries	N/A	N/A	Y	
District Names	N/A	N/A	Y	
Wire Center Boundaries	Passover	Wire Center Name	Y	
Interstate Highways, with designation #	N/A	N/A	Y	
State Highways, with designation #	N/A	N/A	Y	
Major Cities	N/A	N/A	Y	
Water Bodies	Passover	Water Body Name	Y	
Other territory	N/A	N/A	Y	
County Boundaries	Click	County Name	N	
County Names	N/A	N/A	N	If County Name is displayed, County Boundary click feature is disabled
City Boundaries	Click	City Name	N	
City Names	N/A	N/A	N	If City Name is displayed, City Boundary passover feature is disabled
Zip Code Boundaries and Zip Code	N/A	N/A	N	
Numbered Planning Area (NPA) Boundaries and NPA #	N/A	N/A	N	
Exchange Boundaries and Exchange #	N/A	N/A	N	
Local Access Toll Area (LATA) Boundaries and LATA#	N/A	N/A	N	
Airports	N/A	N/A	N	
Landmarks	N/A	N/A	N	

#### -continued

Objects	Behavior	Attributes Displayed	Default View	Additional Information
		Faciliti	ies	
Fiber Routes (IOF only)	Click	Fiber Sheath Attributes of the first sheath	Y	
Fiber Strands (IOF and Loop)	Passover Click	Fiber Strand Name Fiber Strand	N	Shown as result of a query
Central Office Locations	Passover	Attributes Central Office Name	Y	
	Click	Central Office Attributes		
Central Office Names	N/A	N/A	N	If Central Office Name is displayed, Central Office Location passover feature is disabled

20

6.2.1.8.6 Wire Center FMT can provide a default single Wire Center view comprising the Wire Center and partial boundaries of adjacent Wire Centers. FIG. 6 suggests the concept.

Objects	Behavior	Attributes Displayed	Default View	Additional Information				
	Land							
State Boundaries	N/A	N/A	Y					
State Names	N/A	N/A	Y					
(Abbreviation) District	N/A	N/A	Y					
Boundaries	IN/A	IV/A	1					
District Names	N/A	N/A	Y					
Wire Center	N/A	N/A	Y					
Boundaries								
Wire Center	N/A	N/A	Y					
Names	NT/A	NT/A	37					
Interstate Highways, with	N/A	N/A	Y					
designation #								
State Highways,	N/A	N/A	Y					
with designation								
#								
Major Cities	N/A	N/A	Y					
Water Bodies	Passover	Water Body	Y					
Out in the	37/4	Name	37					
Other territory	N/A	N/A N/A	Y					
City Boundaries City Names	N/A N/A	N/A N/A	Y Y					
Railroads	N/A N/A	N/A N/A	Y					
County	Click	County Name	N					
Boundaries	CITOR	County 1 tunic	21					
County Names	N/A	N/A	N	If County Name is				
				displayed, County				
				Boundary click feature is				
				disabled				
Zip Code	N/A	N/A	N					
Boundaries and								
Zip Code Numbered	N/A	N/A	N					
Planning Area	IVA	11/14	11					
(NPA)								
Boundaries and								
NPA#								
Exchange	N/A	N/A	N					
Boundaries and								
Exchange #								
Local Access Toll	N/A	N/A	N					
Area (LATA)								
Boundaries and LATA #								
Tax Area	N/A	N/A	N					
Boundaries and	1472	14/14	11					
Tax #								

-continued

Objects	Behavior	Attributes Displayed	Default View	Additional Information
Airports	N/A	N/A	N	
Landmarks	N/A	N/A	N	
		Faciliti	es	
Fiber Routes (IOF and Loop)	Click	Fiber Sheath Attributes of the first sheath	Y	
Fiber Strands (IOF and Loop)	Passover Click	Fiber Strand Name Fiber Strand	N	Shown as result of a query
Central Office Locations	Click	Attributes Central Office Attributes	Y	
Central Office Names	N/A	N/A	Y	
Remote Terminal Locations	Passover	Remote Terminal Name	N	Shown as the result of a query
	Click	Remote Terminal Attributes		
Remote Terminal Names	N/A	N/A	N	If Remote Terminal Name is displayed, Remote Terminal Location passover feature is disabled
Conduit Runs	Click	Conduit Attributes	N	Currently, this information is available only in the Western States

6.2.8.1.7 Street Level FMT can provide a default view comprising street segments. FIG. 7 and FIG. 8 suggest the concept.

Objects	Behavior	Attributes Displayed	Default View	Additional Information
		Land	l	
State Boundaries	N/A	N/A	Y	
State Names (Abbreviation)	N/A	N/A	Y	
District Boundaries	N/A	N/A	Y	
District Names	N/A	N/A	Y	
Wire Center Boundaries	N/A	N/A	Y	
Wire Center Names	N/A	N/A	Y	
Interstate Highways	N/A	N/A	Y	
State Highways	N/A	N/A	Y	
Major Cities	N/A	N/A	Y	
Water Bodies	Passover	Water Body Name	Y	
Other territory	N/A	N/A	Y	
City Boundaries	N/A	N/A	Y	
City Names	N/A	N/A	Y	
Street Right of Ways	N/A	N/A	Y	
Street Names	N/A	N/A	Y	
Railroads	N/A	N/A	Y	
Parcels	N/A	N/A	N	
County Boundaries	Click	County Name	N	
County Names	N/A	N/A	N	If County Name is displayed, County Boundary click feature is disabled
Zip Code Boundaries and Zip Code	N/A	N/A	N	
Numbered Planning Area (NPA)	N/A	N/A	N	

#### -continued

Behavior	Attributes Displayed	Default View	Additional Information
N/A	N/A	N	
N/A	N/A	N	
N/A	N/A	N	
N/A	N/A	N	
10/1			
	1 aciitti	0.5	
Click	Fiber Sheath	v	
CHEK		•	
Doggover		N	Shown as result of a query
1 assove1		IN	Shown as result of a query
Clials			
Click			
NT/A		W	
N/A	N/A	Y	
37/1	37/4	***	
N/A	N/A	Y	
N/A	N/A	Y	
Click		Y	Currently, this
	Attributes		information is available
			only in the Western States
Click		Y	
N/A	N/A	Y	
Click	Remote	Y	
	Location		
	Attributes		
N/A	N/A	Y	
Click	Optical Node	Y	
	Unit Attributes		
Click	Fiber Sheath	Y	
	Attributes		
	N/A N/A N/A N/A N/A N/A N/A N/A Click N/A N/A N/A N/A N/A N/A N/A N/A Click Click N/A Click Click Click	N/A N/A  Click Fiber Sheath Attributes of first sheath Passover Fiber Strand Name Click Fiber Strand Attributes  N/A N/A  N/A N/A  N/A N/A  N/A N/A  N/A N/A  Click Conduit Attributes  Click Central Office Attributes  N/A N/A  N/A  Click Central Office Attributes  N/A N/A  Click Central Office Attributes  N/A N/A  Click Central Office Attributes  N/A N/A  Click Conduit Attributes  Click Central Office Attributes  Click Central Office Attributes  N/A N/A  Click Central Office Attributes  Click Central Office Attributes  N/A  Click Central Office Attributes  N/A  Click Fiber Sheath	N/A         N/A         N           Passover         Fiber Sheath Attributes         N           Click         Fiber Strand Attributes         N           N/A         N/A         Y           N/A         N/A         Y           N/A         N/A         Y           N/A         N/A         Y           Click         Conduit Y         Y           Attributes         Y           Click         Central Office Y         Y           Attributes         Y           N/A         N/A         Y           Click         Remote Y         Y           Location Attributes         Y           Click         Optical Node Y         Y           Click         Fiber Sheath Y

45

## 6.2.2 Select and Query Visible Graphical and Network Facility Items

#### 6.2.2.1 List Attributes of a Fiber Sheath

		50
Embodiment	List the data attributes of a	
	fiber sheath.	
Description	FMT can provide the user with	
	the ability to obtain defined	
	information about a fiber	55
	sheath. This may be in	33
	conjunction with a fiber strand	
	or a conduit, or as a request	
	for information about a specific	
	fiber sheath.	
Data	See Data Embodiments: Fiber	
	Sheath	60
System Behavior	The system can provide the	
	user with the ability to select a	
	fiber sheath in a graphical	
	environment or on a query	
	screen. For example, a user	
	selects a sheath in the graphical	65
	layer, and FMT displays the	
	ia, ei, and i iii i dispitays the	

#### -continued

fiber sheath's attributes, with an option to further define the search on the query screen environment.
On the query screen, the system can provide multiple parameters for a search. For example, a user may want to view fiber sheath(s) by Manufacturer, Type, Year Placed. Based upon the scope and results of the query, the user can be able to further narrow the search. For example, a user enters Manufacturer and Year Placed as parameters, and FMT displays a listing of all sheaths meeting the criteria. The user can then select an individual sheath to review its data attributes. The user can view the sheath position (compliment) from

<b>-</b> '	_0
-continued	-continued

-continued				
a	the physical strand view		Data	See Data Embodiments: Fiber
Spatial Embodiment	This is viewed as a simple			Strand
	"Attribute Review"	5	System Behavior	The system can provide the user
	embodiment, whereby the user	5		with the ability to select a
	selects a fiber cable in the			fiber strand in a graphical
	graphical environment to review			environment or on a query
	its data attributes. This			screen. For example, the user
	action displays the attributes			* '
	of the selected fiber cable. In			selects a strand and FMT
	addition, "child" tabs or pages	10		displays the fiber strand's
	can be made available for			attributes, with an option to
	review on a fiber cable's			further define the search on
	attribute review panel, e.g., a			the query screen.
	Complements page that shows			On the query screen, the user
				can query the data using
	the complements associated			
	with the particular fiber	15		multiple parameters to define
	cable. Additional tabs that can be			the search. For example, a
	considered as candidates for			user may want to view fiber
	"child" tabs include Logical			strand(s) by Status, Mode,
	Strand and Equipment Locations.			Beginning or Terminating Wire
	Each of these tabs can be			Center. Based upon the
	considered for additional	20		scope and results of the
	functionality, such as providing	20		-
	launch points from Spatial			query, the user can be able to
	to FAS from some of these			further narrow the search.
	child attribute review tabs.			For example, a user enters
				Beginning Wire Center and
	However, some of these launch			Status as parameters, and FMT
	points can be available in	25		displays a listing of all
**	other places in the application	20		fibers meeting the criteria.
User Action(s) in	Select a fiber sheath			č
Spatial	RMC and select 'Attribute			The user can then select an
	review' to see sheath			individual strand to review its data
	attributes			attributes.
Spatial to FAS I/F	Dependent on child tab definitions:		Spatial Embodiment	Definitions for reference:
1	Fiber = none	30	1	OPEDS Strand: Matches the
	Complement = none			OPEDS Sheath/IPID
	Strand = LAUNCH (cable name &			
				Physical Strand: What is in
	strand)			the field - Equipment to splice to
	Location = LAUNCH (CLLI, Area #,			the field - Equipment to splice to splice to equipment
	Location = LAUNCH (CLLI, Area #, &/or loc_clli)			splice to equipment
I/F Type	Location = LAUNCH (CLLI, Area #,	35		splice to equipment Logical Strand: same as physical,
I/F Type	Location = LAUNCH (CLLI, Area #, &/or loc_clli)	35		splice to equipment Logical Strand: same as physical, except without the splices
I/F Type	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1)	35		splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment)
I/F Type	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1)	35		splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created
	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)	35		splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT.
	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1)	35	User Action(s) in	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath
	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)	_	User Action(s) in Spatial	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT.
	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)	35		splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath
.2.2.2 List Attribu	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice	_		splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath
	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes	_		splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes
.2.2.2 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice.	_		splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see
5.2.2.2 List Attribu	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability	_		splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath
5.2.2.2 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined	_		splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button
5.2.2.2 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber	40		splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath
5.2.2.2 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in	_		splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button
.2.2.2 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of	40	Spatial	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name &
.2.2.2 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in	40	Spatial Spatial to FAS I/F	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand)
.2.2.2 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of	40	Spatial  Spatial to FAS I/F  I/F Type	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name &
.2.2.2 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request	40	Spatial Spatial to FAS I/F	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand)
5.2.2.2 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a	40	Spatial  Spatial to FAS I/F  I/F Type	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand)
Embodiment Description	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice.	— <sup>40</sup>	Spatial  Spatial to FAS I/F  I/F Type	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML
5.2.2.2 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber	40	Spatial to FAS I/F I/F Type Scenario: User can search for a fibe	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML
Embodiment Description	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice.	— <sup>40</sup>	Spatial to FAS I/F I/F Type Scenario: User can search for a fibe FAS search, using strand	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML
Embodiment Description	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber	— <sup>40</sup>	Spatial  Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  er strand through name, locations and equipments
Embodiment Description	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber	— <sup>40</sup>	Spatial  Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  er strand through name, locations and equipments strand.
Embodiment Description  Data	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  Location = XML (1)  List the data attributes of a fiber Splice.  FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber Splice	— <sup>40</sup>	Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fib	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  er strand through name, locations and equipments strand. Der strand on
Embodiment Description  Data	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber	— <sup>40</sup>	Spatial  Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  er strand through name, locations and equipments strand. Der strand on
Embodiment Description  Data	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  Location = XML (1)  List the data attributes of a fiber Splice.  FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber Splice	40 45 50	Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fib	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  er strand through name, locations and equipments strand. her strand on ble to see the
Embodiment Description  Data	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  Location = XML (1)  List the data attributes of a fiber Splice.  FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber Splice	— <sup>40</sup>	Spatial to FAS I/F I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fit the spatial tool, and be ab corresponding tabular dat	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  er strand through name, locations and equipments strand. her strand on hele to see the ta in FAS.
Embodiment Description  Data	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  Location = XML (1)  List the data attributes of a fiber Splice.  FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber Splice  tes of a Fiber Strand	40 45 50	Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fit the spatial tool, and be ab corresponding tabular dat Data elements that may b	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  er strand through name, locations and equipments strand. her strand on hele to see the ta in FAS.
Embodiment Description  Data	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber Splice  tes of a Fiber Strand  List the data attributes of	40 45 50	Spatial to FAS I/F I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fit the spatial tool, and be ab corresponding tabular dat	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  er strand through name, locations and equipments strand. her strand on hele to see the ta in FAS.
Embodiment Description  Data	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber Splice  tes of a Fiber Strand  List the data attributes of a fiber strand. This applies	40 45 50	Spatial  Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fib the spatial tool, and be ab corresponding tabular dat Data elements that may b FAS screen:	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  or strand through name, locations and equipments strand. per strand on let to see the tain FAS. e displayed on the
Embodiment Description  Data	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  tes of a Fiber Splice  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber Splice  tes of a Fiber Strand  List the data attributes of a fiber strand. This applies to both loop and Central	40 45 50	Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fib the spatial tool, and be ab corresponding tabular dat Data elements that may b FAS screen:  Strand ID (cable/pair), Lo	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  Ter strand through name, locations and equipments strand. Der strand on De to see the a in FAS. e displayed on the
Embodiment  Description  Data  5.2.2.3 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  Location = XML (1)  List the data attributes of a fiber Splice.  FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber Splice  tes of a Fiber Strand  List the data attributes of a fiber strand. This applies to both loop and Central Office fiber cables.	40 45 50	Spatial  Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fib the spatial tool, and be ab corresponding tabular dat Data elements that may b FAS screen:	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  Ter strand through name, locations and equipments strand. Der strand on De to see the a in FAS. e displayed on the
Embodiment Description  Data	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  Location = XML (1)  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice.  See Data Embodiments: Fiber Splice  tes of a Fiber Strand  List the data attributes of a fiber strand. This applies to both loop and Central Office fiber cables. FMT can provide the ability	45 45 50 —	Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fit the spatial tool, and be ab corresponding tabular dat Data elements that may b FAS screen:  Strand ID (cable/pair), Le the strand is terminated, I	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  er strand through name, locations and equipments strand. ber strand on ble to see the a in FAS. e displayed on the
Embodiment  Description  Data  5.2.2.3 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  Location = XML (1)  List the data attributes of a fiber Splice.  FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber Splice  tes of a Fiber Strand  List the data attributes of a fiber strand. This applies to both loop and Central Office fiber cables.	40 45 50	Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fibe the spatial tool, and be ab corresponding tabular dat Data elements that may b FAS screen:  Strand ID (cable/pair), Le the strand is terminated, I associated with strand (in	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  er strand through name, locations and equipments strand. her strand on ele to see the a in FAS. e displayed on the  cocation(s) where Equipment coluding location,
Embodiment  Description  Data  5.2.2.3 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  Location = XML (1)  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice.  See Data Embodiments: Fiber Splice  tes of a Fiber Strand  List the data attributes of a fiber strand. This applies to both loop and Central Office fiber cables. FMT can provide the ability	45 45 50 —	Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fit the spatial tool, and be ab corresponding tabular dat Data elements that may b FAS screen:  Strand ID (cable/pair), Le the strand is terminated, I associated with strand (in strand, slot, and SCID), I	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  er strand through name, locations and equipments strand. bet see the a in FAS. e displayed on the  cocation(s) where Equipment cluding location, LEAD status and
Embodiment  Description  Data  5.2.2.3 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  Location = XML (1)  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber Splice  tes of a Fiber Strand  List the data attributes of a fiber strand. This applies to both loop and Central Office fiber cables. FMT can provide the ability for a user to obtain defined information about a fiber	45 45 50 —	Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fib the spatial tool, and be ab corresponding tabular dat Data elements that may b FAS screen:  Strand ID (cable/pair), Le the strand is terminated, I associated with strand (in strand, slot, and SCID), I CKID, TIRKS status and	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  er strand through name, locations and equipments strand.  er strand on ele to see the a in FAS. e displayed on the  cocation(s) where Equipment cluding location, .EAD status and CKID, User status
Embodiment  Description  Data  5.2.2.3 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  Location = XML (1)  List the data attributes of a fiber Splice.  FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice. See Data Embodiments: Fiber Splice  List the data attributes of a fiber Strand  List the data attributes of a fiber strand. This applies to both loop and Central Office fiber cables. FMT can provide the ability for a user to obtain defined information about a fiber strand. This may be in	45 45 50 —	Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fib the spatial tool, and be ab corresponding tabular dat Data elements that may b FAS screen:  Strand ID (cable/pair), Le the strand is terminated, I associated with strand (is strand, slot, and SCID), I CKID, TIRKS status and (probably pulldown inclu	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  or strand through name, locations and equipments strand. Der strand on ele to see the ta in FAS. te displayed on the  ocation(s) where Equipment cluding location, LEAD status and CKID, User status ding spare,
Embodiment  Description  Data  5.2.2.3 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  Location = XML (1)  List the data attributes of a fiber splice.  FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice.  See Data Embodiments: Fiber Splice  tes of a Fiber Strand  List the data attributes of a fiber strand. This applies to both loop and Central Office fiber cables.  FMT can provide the ability for a user to obtain defined information about a fiber strand. This may be in conjunction with an item of	45 45 50 —	Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fib the spatial tool, and be ab corresponding tabular dat Data elements that may b FAS screen:  Strand ID (cable/pair), Le the strand is terminated, I associated with strand (in strand, slot, and SCID), I CKID, TIRKS status and	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  or strand through name, locations and equipments strand. Der strand on ele to see the ta in FAS. te displayed on the  ocation(s) where Equipment cluding location, LEAD status and CKID, User status ding spare,
Embodiment  Description  Data  5.2.2.3 List Attribut	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  Location = XML (1)  List the data attributes of a fiber splice. FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice.  See Data Embodiments: Fiber Splice  tes of a Fiber Strand  List the data attributes of a fiber strand. This applies to both loop and Central Office fiber cables. FMT can provide the ability for a user to obtain defined information about a fiber strand. This may be in conjunction with an item of DLE equipment, a fiber sheath,	45 45 50 —	Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fib the spatial tool, and be ab corresponding tabular dat Data elements that may b FAS screen:  Strand ID (cable/pair), Le the strand is terminated, I associated with strand (in strand, slot, and SCID), I CKID, TIRKS status and (probably pulldown inclu working, restricted, defec	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  Ter strand through name, locations and equipments strand. Der strand on De to see the a in FAS. e displayed on the  Decation(s) where Equipment cluding location, LEAD status and CKID, User status ding spare, stive) and CKID,
Embodiment  Description  Data  5.2.2.3 List Attribute  Embodiment	Location = LAUNCH (CLLI, Area #, &/or loc_clli) Strand = XML (1) Location = XML (1)  Location = XML (1)  List the data attributes of a fiber splice.  FMT can provide the ability for a user to obtain defined information about a fiber splice. This may be in conjunction with an item of DLE equipment, fiber strand, fiber sheath, or as a request for information about a particular fiber splice.  See Data Embodiments: Fiber Splice  tes of a Fiber Strand  List the data attributes of a fiber strand. This applies to both loop and Central Office fiber cables.  FMT can provide the ability for a user to obtain defined information about a fiber strand. This may be in conjunction with an item of	45 45 50 —	Spatial to FAS I/F  I/F Type Scenario:  User can search for a fibe FAS search, using strand that are fed by the strand that are connected to that Users can also select a fib the spatial tool, and be ab corresponding tabular dat Data elements that may b FAS screen:  Strand ID (cable/pair), Le the strand is terminated, I associated with strand (is strand, slot, and SCID), I CKID, TIRKS status and (probably pulldown inclu	splice to equipment Logical Strand: same as physical, except without the splices (equipment to equipment) Derived Strand: Path created by WDM EQUIPMENT. Select a fiber sheath RMC and select 'Attribute review' to see sheath attributes Select the 'Strand' tab to see all strands on sheath Select 'Details' push button to see FAS data LAUNCH (CLLI, Cable name & strand) (1) XML  or strand through name, locations and equipments strand. Der strand on ble to see the a in FAS. e displayed on the  cation(s) where Equipment cluding location, LEAD status and CKID, User status ding spare, ctive) and CKID, r types, Mode

#### 6.2.2.4 List Attributes of an Equipment Location

# 30 -continued

		_		
Embodiment	List data attributes for		Data System Behavior	See Data Embodiment: Conduit The system can provide the user
Eliloodinient	Equipment Locations	_	Bysiciii Bellavioi	with the ability to select a
Description	Equipment Locations are defined	5		conduit in a graphical environ-
	as either a Central Office			ment or on a query screen.
	(CO) or a Remote Terminal (RT).			For example, a user selects a conduit in the graphical layer,
	For a specific Equipment Location, FMT can provide a			and FMT displays the conduit's
	defined set of data attributes			attributes, with an option
	(e.g., address, equipment	10		to further define the search
_	housed).			on the query screen.
Data	See Data Embodiments: Equipment			On the query screen, the user can query the data using
System Behavior	Location The system can provide the user			multiple parameters to define
	with the ability to select			the search. For example, a
	an Equipment Location in a	15		user may want to view conduits
	graphical environment or on a			by Type or Length. Based
	query screen. When the user			upon the scope and results of the query, the user can be
	selects an Equipment Location, FMT can provide a			able to further narrow the
	listing of the Equipment			search. For example, a user
	Location's data attributes.	20		enters Type as a parameter,
	From here, the user can be able	20		and FMT displays a listing of
	to view associated attributes,			all types meeting the criteria.
	such as equipment located in the Equipment Location. The			The user can then select a  Type to review all conduits of
	user selects an Equipment			that particular type. Next,
	command button to display a	35		the user could select a
	query screen. The user can	25		specific conduit.
	define the search by entering		User Action(s) in	Select a route conduit feature
	parameters (e.g., type, status).		Spatial	RMC and select 'Attribute review' to see fiber
	Based upon the results of the query (e.g., a Mux type was			sheath attributes associated
	selected), the user can have			with the conduit run.
	the ability to further define the	30	Spatial to FAS I/F	See section 6.2.2.1 for details
	search by selecting the		I/F Type	See section 6.2.2.1 for details
	equipment item to review its	-		
Spatial Embodiment	specific data attributes. User can select equipment			
	location and review its		6.2.2.6 Display Data	Attributes of Landbase Features
	attributes.	35		
	User can opt to review data	-		
	in FAS from the selected location.		Embodiment	List the data attributes of
User Action(s) in	Select equipment location feature RMC and select 'Attribute		Description	Landbase Features FMT can provide the ability
Spatial			Description	for a user to obtain
	review' to see location	40		information about landbase
	attributes			features such as streets, parcels,
	Select 'Details' to see FAS data		a dipin	lakes, rivers, etc.
Spatial to FAS I/F	LAUNCH (CLLI, Area #, LOC_CLLI)		Spatial Embodiment	Simple attribute review of the selected feature
I/F Type	(1) XML		User Action(s) in	Select a land base feature
Scenario:	` '	<b>—</b> 45	Spatial	RMC and select 'Attribute
		— 4J	-	review' to see fiber
User can search for equusing any one of the ab	1			sheath attributes associated
using any one of the at relationship.	ove defined	_		with the conduit run.
User can also select a l				
in spatial number and l		50	6.2.3 Provide Fiber C	Calculation Tools
all the information abo		50		
the above defined structural order. For TIRKS equipments, the above entity			6.2.3.1 Determine Ni	imber of Splices in a Strand
	e correct. But the parent			
		-	Embodiment	Determine the number of solices
			Embodiment	Determine the number of splices in a strand.
object area number/geo	o code can be there.		Embodiment  Description	in a strand. May require a change to the
object area number/geo		55		in a strand.  May require a change to the facility database model.
object area number/geo	o code can be there.	55		in a strand.  May require a change to the facility database model.  Facility database does not
object area number/geo	ta Attributes of a Conduit	55		in a strand.  May require a change to the facility database model.  Facility database does not contain a SPLICE.
object area number/geo	o code can be there.	_		in a strand.  May require a change to the facility database model.  Facility database does not
object area number/geo	ta Attributes of a Conduit  List the data attributes of a conduit  FMT can provide the ability	55	Description	in a strand.  May require a change to the facility database model.  Facility database does not contain a SPLICE.  The number of splices equals the number of sheaths that contain the strand.
.2.2.5 Display Da	ta Attributes of a Conduit  List the data attributes of a conduit  FMT can provide the ability for a user to obtain	_		in a strand.  May require a change to the facility database model. Facility database does not contain a SPLICE. The number of splices equals the number of sheaths that contain the strand. Strand attributes: Continuity,
.2.2.5 Display Da	ta Attributes of a Conduit  List the data attributes of a conduit  FMT can provide the ability for a user to obtain information about a conduit	_	Description	in a strand.  May require a change to the facility database model. Facility database does not contain a SPLICE.  The number of splices equals the number of sheaths that contain the strand.  Strand attributes: Continuity, Splice Type, Default Loss,
object area number/ged .2.2.5 Display Da	List the data attributes of a conduit  List the data attributes of a conduit  FMT can provide the ability for a user to obtain information about a conduit run. This may be in	_	Description	in a strand.  May require a change to the facility database model. Facility database does not contain a SPLICE. The number of splices equals the number of sheaths that contain the strand. Strand attributes: Continuity, Splice Type, Default Loss, Measured Loss
object area number/ged	List the data attributes of a conduit  List the data attributes of a conduit  FMT can provide the ability for a user to obtain information about a conduit run. This may be in conjunction with a fiber	_	Description	in a strand.  May require a change to the facility database model.  Facility database does not contain a SPLICE.  The number of splices equals the number of sheaths that contain the strand.  Strand attributes: Continuity, Splice Type, Default Loss, Measured Loss See Data Embodiments: Fiber
object area number/ged	List the data attributes of a conduit  List the data attributes of a conduit  FMT can provide the ability for a user to obtain information about a conduit run. This may be in	_	Description	in a strand.  May require a change to the facility database model. Facility database does not contain a SPLICE. The number of splices equals the number of sheaths that contain the strand. Strand attributes: Continuity, Splice Type, Default Loss, Measured Loss

	-continued			-continued
System Behavior	When the user selects a strand, the system can indicate the number of splices.  The system can provide this	5		mouse click) a series of points within the graphical view. FMT can indicate the distance.
	function in both a text and graphical environment.	. 10	6.2.3.4 Calculate ar Strand Path	nd Display Anticipated dB Loss of Fiber
6.2.3.2 Provide Dista	nce Between Points on a Fiber Strand			
Embodiment	Provide the ability for a user to select two position points along a fiber strand, and the system can respond with a distance measurement	15	Embodiment  Description	Calculate anticipated dB loss of a fiber strand path. At a user's request, FMT can calculate the anticipated dB loss of a fiber strand path.  **Based on loss data associated with fiber splice (See
Description	along the fiber strand between the two points. FMT can provide the ability for a user to select any two points along a fiber strand to determine the distance	20	Data	6.2.3.1): The attenuation property of a sheath plus the splicing loss. See Data Embodiments: Fiber Sheath - Attenuation
	between the points. The distance calculation can include loop distances along the fiber strand path.	25	6.2.3.5 Input Loss	and Locate Fiber Cut
Data System Behavior	See Data Embodiments: Fiber Sheath FMT can provide the user with	-	Embodiment	Input Fiber Loss and locate the Fiber Cut
System Beliavior	the ability to view a fiber strand route in the graphical layer. The user can be able to select (i.e. mouse click)	30	Description	User can input the loss of a fiber and the system can generate where the fiber cut is located.
Spatial Employdiment	two points along the fiber strand path. FMT can indicate the distance.		Data	This can be based on the best data which is available. First choice is actual splice loss,
Spatial Embodiment	Calculate sheath distance along a route between two points. Calculation is a proration of geographic distance and database lengths; where/when intelligent loops features exist (planned for Spatial Age EWO), the sheath distance can calculate based on loop location & lengths, and span lengths.	35 40	Spatial Embodiment	second choice is default loss.  User can also be shown the measured loss, but no logic can be performed against the measured.  User Interface (Outage Location function) for user to select fiber strand (fiber name, strand), indicate ring type, side, test location (area # or loc/clli), and enter db loss OR distance reading. Spatial calculates cut location using
6.2.3.3 Provide Dista	ance Between Geographic Points	45	User Action(s) in Spatial	default loss values, and/or actual loss values if present.
Embodiment	Provide the ability for a user to perform a distance measurement between any two		Spatial to FAS I/F I/F Type	Read stored loss values for fiber strand in FAS. (2)
	points within the current graphical view of the landbase and network facilities.	50	6.2.3.6 Generate Re	estoration Order Based On System/User
Description	FMT can provide the user with the ability to select any two points within the current graphical view to determine the	55	Embodiment	Generate Restoration Order/Assigned Restoral Order
	distance between the points. For any two points within the landbase, a user can have the ability to determine distance between the points. The system can round all distance measurements to the	60	Description	FMT can generate or assign a restoration order that is based on the system or user. It can generate a fiber strand restoration priority list from a graphically selected fiber sheath within an average of 60
Data System Behavior	nearest foot or meter. Systems: OPEDS FMT can provide a view of a fiber strand path in the		Data	seconds or less from a web user interface. Need info by sheath and then by ribbon and then by strand.
	graphical environment. The user can be able to select (i.e.	65	Spatial Embodiment	Provide user interface to select one or more fiber sheaths.

33			34			
	-continued		-continued			
Spatial then passes strand information (by sheath, ribbon, & strand) to FAS.			Spatial Embodiment  Build necessary physical & logical strand data from OPEDS data. Provide an interface to FAS to acquire logical strand data.			
6.2.4 Generate Fib	ner Schematics		Data elements that should be displayed on the FAS screen:			
6.2.4.1 Use Automatic Schematics Tool		10	Same as 6.2.2.3. Source for all the data elements for this embodiment:			
Embodiment	Add system generated schematics	-	Same as 6.2.2.3.			
Description	The system can generated schemates The system can generate high- level graphical view of facility routes with less detail and no landbase. These "stick" schematics should provide the user with a general view of the location, number,	15	See 6.2.2.3  6.2.5.2 Provide Connectivity Between Fiber Strand an Equipment Slot			
	and size of fibers in an area, allowing for easy viewing and analysis of a large geographical area.	20	a fiber strand and DLE equipment and display the data attributes for each			
Data	Data Source (Primary, Description Secondary)		associated item of equipment and fiber strand.			
General Discussion	Area of concentration is fiber since not much copper relief is being done (or authorized)	<b>-</b> 25	Description  For a specific strand, FMT  can identify the DLE equipment  in which the strand originates  and terminates. FMT can  also provide a defined set of			
Spatial Embodiment	anymore. Types of schematic generation desired are handled by 'view' capabilities in COTS.	30	information regarding each of these items of equipment.			
6.2.4.2 Use Manua	al Schematics Tool	35	strand(s) that is/are either terminating or originating. FMT can also provide a defined			
Embodiment	Allow for user created schematics	_	Data See Data Embodiments: DLE Equipment,			
Description	The system can allow a user to create or import existing "stick" schematics, which		Multiplexer(MUX), LGX, DSX, DLC, ONU, NMLI, Repeater Shelf Switch			
	have no underlying landbase.	40 -	System Behavior The system can provide the			
6.2.5 Integrate Fiber Related Data			user with the ability to select a strand in a graphical environ- ment or on a query screen, and view the results in a tabular			
6.2.5.1 Add Fiber	Strand and Derived Wavelength Data	45 -				
Embodiment	Allow for Fiber Strand assignment(utilization) data to be added into a source database.		boundaries. When the user selects a strand, FMT can provide a list of all equip-			
Description	FMT can establish a source database for fiber strand	50	upon the query) connected to			
General Discussion	assignment. "FMT" can be the de facto data source for fiber strand data. What may be most important is		the strand. When the user selects an equipment item or type, the system can provide the equipment item's defined			
	not 'assignment' type data but instead 'utilization' type data. Spatial creates 'physical strands' from OPEDS fiber sheath data using complements. Spatial also creates logical	55	type is selected, all items defined by the type. The user can then be able to select an equipment item and review its informational attributes.			
	strands, or assemblies, from the physical strand data. An assembly essentially runs from 'port to port', providing end-to-end connectivity of a single strand. Spatial can provide an interface	60	The system can provide the user with the ability to select a DLE equipment item on a query screen. A user can select an item of DLE equipment and indicate the set of information desired. This may			
	to FAS for this 'logical strand', or assembly, data.	65	include a listing of all fiber strands terminating to or			

#### -continued

# 36 -continued

Spatial Embodiment	originating from the item of equipment and/or the equipment's informational attributes. Further May only need to be able to get to an equipment location and see equipment details in FAS. Drill down from fiber sheath to strand to equipment location, then launch FAS.
User Action(s) in	
Spatial	
Spatial to FAS I/F	LAUNCH (CLLI, area #, LOC_CLLI)
I/F Type	(1) XML
Scope for FAS:	

performs appropriate query against FAS and the highlights SCID path and associated locations.

User selects fiber strand in Spatial and requests a SCID trace; Spatial

User searches for a piece of equipment; FAS displays selected information, including SCID; user can then see all other equipment

which is also associated with the SCID.

6.2.5

6.2.5.4 Provide LEAD and TIRKS Circuit IDs

FAS should store the connectivity information between logical

- fiber strand and equipments (LEIM, TIRKS and FOX). At a high level. FAS should be able to answer the following question.
- 1. For any given logical fiber strand, list all the equipments connected to it.
- 2. For any given equipment, list all the logical fiber strand connected to it.
- 3. For any given logical fiber strand, list all the locations connected to it.
- 4. For any given location, list all the logical fiber strand connected to it.

A logical fiber strand is a fiber strand between two locations (area number). A location (area number) can have multiple CSA/location clli. A CSA can have multiple loc-ids. A loc-id can have multiple equipments.

Scenario:

User can search for an equipment in FASWEB, using any one of the above defined relationship.

User can also select a location (area number) or logical fiber strand in spatial and FAS can display all the information about that location or the fiber strand in the above defined structural order. User can select strand and see all equipment, sheaths, and locations associated with the strand. Conversely the user can select a piece of equipment and see all strands and other pieces of equipment with which it is connected.

User can select strand and see all equipment, sheaths, and locations associated with the strand. Conversely the user can select a piece of equipment and see all strands and other pieces of equipment with which it is connected.

# 6.2.5.3 Provide SCID Relationships to Fiber Strand and Equipment Slot

Embodiment	Provide SCID Relationships
	to Fiber Strand and
	Equipment Slot.
Description	System should be able to
-	form a SCID relationship
	between a Fiber Strand and
	an Equipment Slot in order to
	identify it.
Data	FAS tool can collect info
	from TIRKS as to relationship
	between SCID and strand(s)
	and equipment. AI: where is
	data in TIRKS.
Spatial Embodiment	FAS provides Spatial with
	minimum LOC_CLLI, cable id
	& strand in order to kick
	off a fiber trace of the strand
	and equipment of interest.
FAS should capture the relation	onship between fiber strand and equipment
in the form of a SCID (Sonic	circuit ID) relationship.

Embodiment Provide CKIDs from LEAD
and TIRKS

Description System can generate CKIDs
from LFACS or LFACS and
TIRKS by integrating fiber
assignment data.

User searches for fiber strand; FAS displays assignment data based on

data from these systems. See section 6.2.2.3

Data elements that should be displayed on the FAS screen:

Source for all the data elements which are required for this embodiment:

See 6.2.2.3

25

35

40

### 6.2.5.5 Capture Fiber Diversity Information

)	Embodiment	Capture Fiber Diversity Information
	Description	Once a user has determined that
	•	a strand is diversely routed
		or a site is diversely fed,
		FMT can capture the diversity
		information about the Fiber
5		and capture it into the
		database. The user can select
		a type of diversity from a
		list of diversity types
		such as sheath, route, CO.
	Data	System: OPEDS
		Spatial embodiment: user can
'		update FAS database with
		diversity information. If
		the user determines that
		something is diverse using
		Spatial, then Spatial can update
		FAS with that data.
•	A SINGLE FIBER STAN	D IS NOT DIVERSELY ROUTED, BUT
	A STRAND CAN BE DIV	ERSELY ROUTED COMPARED TO
	ANOTHER STRAND. EQ	QUIPMENT CAN BE FED DIVERSELY,

A STRAND CAN BE DIVERSELY ROUTED COMPARED TO
ANOTHER STRAND. EQUIPMENT CAN BE FED DIVERSELY,
THUS DIVERSITY DATA SHOULD BE STORED FOR A PIECE
OF EQUIPMENT
Scenario:

User determines that a piece of equipment is of a particular diversity type; user navigates to appropriate FAS webpage and enters diversity type (by selecting from a list of values)

#### 6.2.5.6 Capture Fiber Connections from FOX

60	Embodiment Description	Capture Fiber Connections from FOX FMT can integrate with FOX to obtain where the Fibers
00		connect.
		User can request FOX data
		for presentation. User can then
		be able to compare FOX data
		against FAS data by
		matching on location and bay/
65		panel/jack. No other logic
		may be utilized.

	37		,241 <b>D</b> 2	38
	-continued			-continued
Description Scope for FAS:	FMT can integrate with FOX to obtain where the Fibers connect.	5	Data	of the source documents should be made as ease as possible. See section 7 Also capability to upload fiber
	ermation about the connectivity between logical		Scope for FAS:	strand attributes into FAS.
fiber strand and equipm Scenario:	ent from the FOX system.	10	From a user's perspective with the addition that the	this embodiment can be the same as 6.2.2.3 user can also have a means of bulk loading
devices based on the dat	ogical fiber strand and see all the connected to obtained from FOX. a device and see all the equipments attached	10	data into FAS based on da source databases. Scenario:	tta which does not exist in the other
User can also select a fil equipments attached to User requests FOX data	ber strand in spatial and see all the it based on the data we got from FOX.) . FAS presents FOX data for a location next to	15		be displayed on the FAS screen:
	nent data for that location. riate data in the User section of Fiber Strand			ments which are required for this embodiment:
6257 Canture	a LOC/CLLI and Address from LOC/	20	See 6.2.2.3	
CLLI System	a Boolega una radicio nom Bool	20	6.2.5.11 Manage	Out of Franchise Fiber and Equipment
Embodiment	Capture a LOC/CLLI and Address from LOC/CLLI System	25	Embodiment	Develop a means of managing out of franchise fiber and
Description Data	FMT can capture, as needed, all LOC/CLLI and Addresses from the LOC/CLLI System. System Embodiments: LOC/CLLI		Description	equipment The telecommunications company may own fiber optic cables and equipment in areas
	Easement/ROW Information for Locations  Capture and Retrieve ROW/	30	Data	outside of the 1600 wire centers. This fiber needs to be shown graphically, and the fibers can be tracked in the tabular tools.  The data elements are identical to data for fiber and equipment in franchise.
Description	Easement data from BETS User can enter the ROW# into the planning layer of FMT and the appropriate data from BETS is retrieved.	33	This information ma (EWO and LEIM, e	ry first be entered in the source databases
6.2.5.9 Generate Wire Centers	e Land Base for Non-OPEDS Converted	40	6.2.5.12 Display ment	and Identify CLEC Sheaths and Equip-
			Embodiment	Display CLEC sheaths, strands, and equipment in the
Embodiment	Generate land base for non- OPEDS converted wire centers with the location of central offices, equipment sites and x-boxes from the existing OPEDS land base data.	<ul><li>45</li><li>50</li></ul>	Description	graphical and tabular tools Competitors may have the right to utilize structures (pole lines, ducts, manholes, cabinets, etc.) Wherever these facilities are identified and entered into a source system by engineering, those facilities
6.2.5.10 Development Sources	p Mechanized Processes from Legacy Sys-			must be properly identified in FMT. Facilities which are identified in OPEDS as belonging to
Embodiment	Develop a mechanized process	55		other companies may be identified as such in FMT.  Equipment which is identified in LEIM and in TIPMS.
Description	to load data and manage conflicts from separate legacy system sources and user input from local records.  The system can determine an appropriate source to use to	60		in LEIM and/or TIRKS must be identified as such. The LEIM equipID can carry the intelligence as to which equipment belongs to CLECS, but the standard has not yet
	provide existing fiber and equipment attributes. Conflict identification of database and source documents should be easily documented	65		been set; as a result, a means of parsing EquipID's and comparing them against a ruleset for determining ownership must be created.
	and feedback to the keepers			

	try of Fiber Loss Data Manual Entry of Fiber Loss Data		6.2.6.4 Display
			Embodiment
Embodiment  Description	Allow user to enter actual measured loss for a fiber strand If a user has measured the loss	5	Description
2 10011	for a fiber strand, that user should be able to enter that loss information for that strand.	10	Scope for FAS:
6.2.5.13.2 Allow A	automatic Entry of Fiber Loss Data		Display the slot and can All equipment from Lattributes as shown too Scenario:
Embodiment	Allow user to upload measured loss data for a fiber strand	15	User can select the eq
Description	If a user has measured loss data stored electronically, the		a location from Spatia
	system can upload that data and store it.	20	6.2.6.5 Locate
6.2.5.14 Display M	Measured Loss		Embodiment Description
Embodiment Description	Display Measured Loss User can view the measured loss via a webpage or spatial	25	Spatial Embodiment
6.2.6 Provide Fibe	ers and Related Equipment Search and	30	
1 0	abinets for Specified Equipment Loca-		
on			Scope for FAS:

Embodiment Display Structures for Specified for Specified Equipment Location. Description System should be able to display appropriate structures that relate to the specified equipment location that is specified by the user.

### 6.2.6.2 Display Devices for Selected Structure—Filter by Туре

Embodiment	Display Devices for Selected Structure and Filter by
Description	Type User can select a structure and the system can display the devices by type.

## 6.2.6.3 Display Selected Device Attributes

Embodiment	Display Selected Device
	Attributes
Description	User can select a device from
	the screen or either by
	navigation or via a search,
	and the system can display the
	attributes for that device.
Data	Data Embodiments: All devices
User can search for equipme	ent by using different FAS search
functionalities. Once equipm attributes of the equipment.	nent is selected, FAS can display all the
attributes of the equipment.	

#### 40

## ay Device Slots and Related Circuits

Embodiment	Display Device Slots and
ξ.	Related Circuits
Description	User can select a device, cir-
	cuit, or fiber from the screen or
	search for one, and the system
	can display the appropriate
	device slots and related circuits.
0 Scope for FAS:	

circuit information for a given device. LEIM and TIRKS can be loaded into FAS; same oday in FAS can be displayed

quipment through FAS search or through selecting

#### e Equipment by Address

Embodiment	Locate equipment by address
Description	User can enter an address
	and the system can display the
	equipment associated with
	that address.
Spatial Embodiment	Multiple embodiments 1) configure
	a Equipment Location
	locate - search by address,
	area #, loc_clli 2) configure a
	street address locate 3) launch
	FAS from equipment location 4)
	provide Launch & Locate capability
	from FAS for street address
Scope for FAS:	

 $35\,\,$  FAS should allow the user to search for a location using the address. User can search against address, CLLL, or AreaNumber/GLC. Address includes all possible address attributes, including House Number, street, floor/suite Scenario:

Provide a search for searching a location by address. Data elements that should be displayed on the FAS screen:

Display all attributes of a location (CSA/locid)

60

65

6.2.7 Provide Fibers and Equipment Utilization Monitor-45 ing

## 6.2.7.1 Provide CSA Utilization by Service Type

50	Embodiment	Provide CSA Utilization by Service Type
55	Description	CSA fill data can be created in a similar fashion as the Crossbox Report, which is currently under development in FAS. Users can determine which systems are fully utilized and which systems are underutilized.
	Data	Built on existing interface between FAS and LEAD.

### 6.2.7.2 Provide CSA Alerts to FACILITY PLANNERSs

Embodiment	Provide FACILITY PLANNERS
	with some sort of an
	alert of a CSA

Description	Users can receive of CSA when the to FMT and via e	ey are logged in
Data	Data Description	Source (Primary, Secondary)

#### 6.2.7.3 Determine Fiber Strand Utilization

#### 6.2.7.3.1 Determine Whether Physical Strand is Assigned

D ( 1 1 d 1 1 1 1
Determine whether physical
fiber strands are assigned,
spare, or defective.
The system can store information
which indicates whether
a physical fiber strand is in
use or can be used to provide
service.
Assigned indicates that a fiber
is either working or
reserved. Assigned in analogous
to saying that a fiber is
"lit".
Spare indicates that no traffic
is transmitted on the fiber
strand.
Defective indicates that the
fiber strand is currently
incapable of transmitting data.
See Data Embodiments: Fiber
Strand

### 6.2.7.3.2 Determine Physical and Derived Fiber Strand Utilization

Embodiment	Determine which physical and	
	derived fiber strands are	
	in use	
Description	The system can store information	
	which indicates if a fiber	
	strand is connected to Wave	
	Division Multiplexing	
	equipment (WDM or DWDM) which	
	allows data to be	
	transmitted on several distinct	
	wavelengths (lambdas). The	
	system can also store information	
	as to which lambdas are	
	assigned, spare, or defective.	
Data	Assigned indicates that a	
	physical or virtual fiber strand is	
	either currently transmitting	
	data or reserved.	
	Spare ad Defective are defined	
	in 6.2.7.3.1.	
	See Data Embodiments: Fiber	
	Strand	
Scope for FAS:		
*		
	- # of Lit Derived and Physical	
	of Derived and Physical fibers)	
Data elements that sl	hould be displayed on the FAS screen:	
Donast oon includes		
Report can include:	rs; number lit; number spare; number defective;	

#### 42

6.2.7.3.3 Determine Carrier Signal Level Utilization for a Strand

5	Embodiment	Determine Carrier Signal Level Utilization for a Strand
	Description	The system can store information
		which indicates if a fiber
		strand is connected to Wave
		Division Multiplexing
10		equipment (WDM or DWDM) which
		allows data to be
		transmitted on several distinct
		wavelengths (lambdas). The
		system can also store information
		as to which lambdas are
15		assigned, spare, or defective.
13	Data	Assigned indicates that a physical
		or virtual fiber strand is
		either currently transmitting
		data or reserved.
		Spare ad Defective are
		defined in 6.2.7.3.1.
20		See Data Embodiments: Fiber Strand

Provide matrix report similar to Xbox and/or CSA report. Rows consist of fiber by mode, physical, and derived fiber strands. Columns consist of services such as NMLI, customer <sup>25</sup> OCn ring, Company OCn ring, dry fiber, etc. User can select points in Spatial and designate them as monitoring points; this report can be run at any location and at a monitoring

6.2.7.3.4 Determine DS0 Equivalent Utilization for Virtual 30 and Physical Fiber Strands

Embodiment	Determine DS0 Equivalent
	Utilization
Description	The system can store infor-
	mation which translates the
	circuits which are working
	on a fiber strand to the
	equivalent number of DS0's
	based on conversion values.
Data	Assigned indicates that a
	physical or virtual fiber strand is
	either currently transmitting
	data or reserved.
	Spare ad Defective are defined
	in 6,2,7,3,1.
	See Data Embodiments: Fiber Strand

Embodiments may use DS3 equivalent rather than DS0 equivalent. Based on categorizations in previous embodiment and a conversion table, the number of DS3 equivalents for a strand can be determined.

#### 6.2.7.4 Determine Fiber Sheath Utilization

	Embodiment	Determine Utilization of each Fiber Sheath
55	Description	User can select a fiber sheath to see the utilization.
	Data	See Data Embodiments: Fiber Sheath
	General Discussion	Net result - utilization calcula- tions are done using data stored in or available to FAS.
50	Spatial Embodiment	User may select a fiber strand(s) (via fiber sheath) on which to perform utilization. Spatial passes logical fiber information (cable id, strand) to FAS to perform utilization
55		function.

if the monitor level is in danger. There is no 'automatic notification' of alerts in Spatial; it is up to the user to invoke this theme whenever the user desires to do so.

B) When this "Cross Section Alert" theme is invoked,

## 6.2.7.5 Determine Utilization Trend Analysis

# 44 -continued

				-continued
		_		Spatial queries a view/table
Embodiment	Determine Utilization Trend			provided by FAS to set the
	Analysis	5		required displays for the
Description	User can view the current or	,		Monitor Point feature.
	past trends of utilization			User can select the monitor feature and launch FAS to see
	among a given search parameter, i.e. district, state, etc.			details for the selected
Scope for FAS:	i.e. district, state, etc.			cross section.
<u> 500ре ют тию.</u>			Spatial to FAS I/F	A) NOTIFY (monitor id, CLLI,
For a location and a	monitoring point. FAS can keep high level	10	•	list of cable id/strand,
utilization data for t				min/max)
		_		B) QUERY Table (monitor
				id, group status)
6.2.7.6 Determin	e Fiber Cross-Section Alerts			C) LAUNCH (CLLI, list of cable id/strand)
		1.5	I/F Type	A) (1) XML (new action = NOTIFY)
			21 1JPC	B) (2) View/table (required)
Embodiment	Determine Fiber Cross-Section Alerts		Embodiments can use th	ne spatial age, to define the monitoring fiber
Description	User can receive an alert or		cross-section group. Spa	atial age can find the fiber strands, which
	warning for specified fills on			ned group, and can send the FAS strand data
	strand and bandwidth utiliza- tion once they have reached			onitoring that group based on the fiber
	the specified number that is	20	utilization logic	echanism to provide this information to
	set as the default or warning		Spatial age.	echanism to provide this information to
	level. These alerts can be			apability to create a monitoring spatial group.
	based on fiber sheath and on		It may always be done f	
	cross section (route, a com-		But FAS may have the c	capability to define what is Red, Yellow and
	bination of fiber sheaths in the	25	Green.	
	same geographic area).	23		al engine can send a list of elements to FAS
	Ex. "Send me an email notice when this cross section has			lert information. That can enable Spatial to
	only 6 spare fibers remaining."		display the data in a col-	or coded form.  I send list of fiber strand and FAS can send the
	Note: Spare should not include		A / A	of for those FAS strand. Based on that Spatial can
	defects.		display a graphical view	
Data	Default values and warning	30		•
	level can be set for specified			
	fills; and users can receive			section in the spatial tool. Once a cross
	these warnings once the data			al tool can provide FAS with the entire
Spatial Embodiment	has reached or past that level.  Provide a feature, "Monitor			, which is part of that cross section.
Spatial Efficoamient	Point", that is placed by the	2.5		d utilization the corresponding cross section  S can also provide alerts on the main page based
	user. This feature identifies	33	on the cross section stat	
	one or more fiber sheaths to be		Data elements that shou	ld be displayed on the FAS screen:
	monitored. User may define			
	sheaths for inclusion			cross section, what data elements may be
	(association with) in the fea- ture by selecting sheaths or by		displayed in FASWEB i	
	drawing a polygon around	40		section) can be shown along with its various
	desired sheaths. User may			efined in sections 6.2.7.3
	optionally define which speci-			Id include Locations, and user can suppress alerts oression for Xbox in FAS today.
	fic strands of this group they			lements which are required for this embodiment:
	wish to monitor. User also		Bothee for all the data e	rements which the required for this embodiment.
	defines the maximum fill (or	45	See section 6.2.7.3 for d	lifferent types of utilization. Alerts can
	minimum spare) threshold to issue an alert. Frequency of	15		n based on physical strand.
	monitoring is specified by		For a Location, FAS ma	y have knowledge of strands which are associated
	(user specified or default		with it based on 1)OPEI	DS sheaths which feed an electronics location
	frequency)		and 2) Spatial selection	of one or more sheaths in the same general
	A) Spatial passes this			is a natural relationship between sheath and
	information (monitor id,	50	logical strand.	
	CLLI, & list of cable id			
	and strand, min/max, etc.) to FAS for monitoring.			
	Spatial provides a "Cross		6.2.7.7 Determin	ne MUX Utilization
	Section Alert" theme (view)			
	customized to show only those	55		
	features of interest to a user	55	Embodiment	Determine MUX Utilization
	who wishes to see status of		Description	User can determine MUX utili-
	these features. The Monitor			zation to determine fiber
	Point feature is set to display			utilization This is "iView" mux utili
	in one color if monitor level is safe and a different color			This is "iView" mux utili- zation which is based on a worst
	if the monitor level is in	60		case combination of LEIM.

55 -			-
00	Embodiment	Determine MUX Utilization	
	Description	User can determine MUX utili-	
		zation to determine fiber	
		utilization	
		This is "iView" mux utili-	
60		zation which is based on a worst	
00		case combination of LEIM,	
		LEAD, TIRKS, and User DS1	
		and above data. User can	
		pull reports based on this	
		utilization as well as see	
		this data in the existing	
65		FAS view of equipment.	
_			_

#### 6.2.7.8 Monitoring Point

## 46

#### -continued

Embodiment Description	Monitoring Point Spatial may need to allow user to place a monitoring Point to see and define strands to be monitored for utilization at a particular route cross-section. Locations are, by default, Monitoring Points. The user can define additional Monitoring Points and assign those points a name and some comments.

#### as maintenance log, such as notes, which can be captured with updated date and user name

#### 6.2.8.2 Allow User to Determine Fiber Strand Diversity

10	Embodiment	Determine Diversity of a Fiber
10	Description	Strand A strand is route-diverse when
		it is not in or on the same
		supporting structure (conduit).
		A strand is CO-diverse when it is route-diverse and
1.5		terminates in two Central
15		Offices.
		Users can determine whether a
		fiber strand is non-diverse,
		CO-diverse or route-diverse
		with tabular and graphical
20	Data	data.
	Data	Systems: OPEDS There may be a desire to know
		the relationship of one
		system assembly to another
		and the diversity of one system
25		assembly to another.
23	Spatial Embodiment	Spatial provides a 'diversity
		check' trace function to allow user to determine 'sheath
		level' diversity. The
		diversity check provides a
		visual (via highlights) indicator
30		as well as trace results dialogs
		showing 'common' paths in
		the trace. 2) A diversity check
		can also be launched from
		FAS. FAS provides a set (pair) of logical fibers (cable
35		name(s), strand(s)), each
33		terminating loc/clli (or area #),
		and LGX port data (this may
		need to be accessed via
	G	connector type 2).

## 6.2.7.9 Xbox and CSA History and Trending

Embodiment	Xbox and CSA History and
	Trending reports
Description	Maintain high level Xbox and
	CSA utilization data for
	up to 5 years
Data	Based on the original concept
	for the Xbox reports,
	monthly data for Xbox and CSA
	can be maintained for 24
	months; quarterly data can be
	maintained for an additional
	3 years. This data is essen-
	tially the summary row for each
	of the services for the Xbox
	or CSA.
	Based on past utilization,
	generate trendline so that user
	can estimate future needs.

6.2.8 Provide Fiber Tools and Reports	
6.2.8.1 Generate Equipment Site Activity Lo	g

Embodiment Description	Create a Site Maintenance Package A site maintenance package
	consists of easement
	information for a site (loca-
	tion clli) and the structures,
	which exist there. The user
	also needs to be able enter
	comments along the lines of
	where to park, restrictions, etc.
Data	Easement, any comments/re-
	strictions, all TEO and/or jobs
	Filed by CSA
	Need additional jobs besides
	those which are stored in
	LEIM (site prep job, etc.)
Spatial Embodiment	MOSTLY FAS, but not necessarily
	all. User can Launch
	FAS to see Location.
Scope for FAS:	

Spatial can provide a list of strand and FAS can provide the list of associated equipment, shelf and slot for that strand. FAS can allow the user to launch spatial for given equipment. FAS can send the list of strands based on the scid, which allow spatial to display the ring.

Scope for FAS:

Based on 6.2.5.5 user can enter diversity information for a piece of equipment. Scenario:

User selects location in Spatial. User navigates to FAS and looks up fiber information for equipment at that location. In Spatial user then runs a diversity check for the fiber strand(s). Once user determines diversity type user enters that type in the FAS equipment screen. Diversity type is from LOV or "other" which allows the user to manually enter some other value. Data elements that should be displayed on the FAS screen:

Equipment (from FAS equipment database), feeding fiber strand(s),

Source for all the data elements which are required for this embodiment:

FAS equipment database (LEIM and TIRKS), Spatial Age, User

Site maintenance package is maintenance package information for a CSA. All the data may be manually updated/entered by users FAS MAY MAINTAIN A LIST OF LRS'S WHICH ARE ASSOCIATED WITH A LOCATION. HIGH LEVEL DATA FROM THE LRS, INCLUDING EWO NUMBER, SCOPE OR WORK, JOB CLOSED DATE CAN BE STORED. THIS DATA MAY BE AUTOMATIC, ASSUMING THAT USER PROPERLY ENTERS ATTRIBUTES IN LRS. USER MAY ALLOW ENTER COMMENTS FOR THE LOCATION. USERS CAN ALSO ENTER ADDITIONAL HISTORICAL DATA ALONG THE SAME LINES AS THAT WHICH CAN BE AUTOMATICALLY GENERATED USING THE LRS. Scenario:

### 6.2.8.3 Assign Restoration Priority for a System Assembly

Assign a restoration priority
for a System Assembly.
System can assign a priority
based on a maintained list of
values. This priority number

User can select a CSA either through search or through spatial. Once a CSA is selected, then user can enter certain information 65

47

#### -continued

can be used when the restoration order is generated

restoration (see 6.2.3.6

Based On System/User)

in the event of an emergency

Generate Restoration Order

-continued

For a given state. FAS can store all the valid SCIDs and also can be able to find the next SCID. FAS can provide a mechanism to assign a SCID based on the FACILITY PLANNERS request. Rule for SCID's may be as follows:

48

6 characters, N1–N6. N1 indicates company division, typically N for network N2 indicates state

this embodiment:

N3-N5 is alphanumeric N6 designates ring type (L, G, R, P for Loop, Smartring . . . ) Source for all the data elements which are required for

Existing SCIDs from TIRKS and LEIM

Strand

6.2.8.4 Assign Reservation for a Fiber Strand

User can reserve fiber for a LRS.
The word Reserve is now replaced with the concept of "Interest."

Assign Reservation for a Fiber

An interest in a strand is established via a LRS.

User can establish an "interest" in a fiber strand via a LRS. An interest indicates that the strand may be used in the future if the LRS is executed, but there is not guarantee that the strand can be used, thus it is not reserved. Interests are only created from within FAS, not from LEIM, TIRKS, or any other system. Data elements that should be displayed on the FAS screen:

See LRS and 6.2.2.3

Embodiment

Description

# 6.2.8.5 Provide Numbering Administration Tools6.2.8.5.1 Add System Numbering Tool

Embodiment Add an automated DLC/mux numbering tool Description The system can provide a means to administer DLC system and mux numbers. FAS can stored existing system numbers and planned system numbers by equipment type. FMT can not attempt to predict next usable number. Scope for FAS: Four alpha numeric characters after the # symbol is the system number. FAS should develop a system number maintenance module. System number may be unique for a given WC. FAS should provide mechanism to propose new system number and display existing system numbers. Numbering scheme is determined by equipment type; system helps user understand which numbers within a scheme are in use and which ones are available Scenario: During the LRS lifecycle the user determines that a new system must be created. User enters appropriate equipment data (including category) in the LRS and then wants to know what the system number should be, so he clicks a "find system number" link. Data elements that should be displayed on the FAS screen: Equipment type, used system number(s), next available system number Source for all the data elements which are required for this embodiment:

#### 6.2.8.5.2 Add SCID Administration Tool

LEIM

Embodiment Add a tool for managing SCID
assignments

Description The system can provide a
means of administering SCID's
for districts and throughout the company.

### SCID Log Tool—General

FMT can provide users the ability to view SCID assignments, select a new SCID assignment, and to unassign a SCID that has not been or no longer used. FMT can also provide Staff Support persons the ability to establish rules for SCID assignments. SCID can have a Status transition as follows: SCID Status Codes:

25	CODE	DESCRIPTION
	N	New, never assigned or used - available for assignment
	H	Hold, do not assign
	A	Assigned
	W	Working/Used
30	X	Deleted - not found working
30	U	Unassigned

#### SCID Status Transition:

35				
	FROM STATUS	TO STATUS	ACTION	DESCRIPTION
	<null></null>	N	ADD SCID	Process that adds SCIDs to log to make available for use.
40	<null></null>	Н	HOLD SCID	Manual DBA addition of SCIDs to Log or status change.
	<null>, N, U, or X</null>	A	ASGN SCID	Assigned for use. SCID added or updated in SCID_LOG. If SCID had a status of U or X, the log data is stored in
45	any	W	UPDATE SCID LOG	SCID_History before update. Batch process run periodically to determine if SCID is still in FMT data. SCID is found in FMT (LEIM or TIRKS) data. SCID added or updated in SCID LOG.
50	A	U	UNASGN SCID	User that initially assigned SCID determines that it is not required and Unassigns it. SCID Status is changed from 'A' to 'U' and status date updated.
55	W	X	UPDATE SCID LOG	Batch process run periodically to determine if SCID is still in FMT data. SCID is not found in FMT (LEIM or TIRKS) data.

### SCID Log Tool—ASGN SCID

60

65

Embodiment
Description

Provide New SCID Assignment
User can select ASSIGN SCID
function that can allow input
parameters to be selected or
changed and the next available

49

#### -continued

	SCID to be assigned. The next
	SCID assignment that meets
	the parameters can be assigned
	the lowest unassigned SCID.
Data	The data to be selected by the
	user to determine next SCID
	assignment is a follows:
	1) State
	2) District
	3) SCID Type
	The data to be possibly captured
	for the SCID assigned is:
	1) User
	2) Date
	3) LEG Installation ID
	4) Equipment
	5) Authorization Number
	6) Address
	7) Service Date
ASGN SCID	Upon selecting the ASGN SCID
Screen	function, the user may be
	presented with an ASGN SCID
	screen. Item are as follows:
	1) State - drop-down of 9
	BST States defaulted to user's
	State
	2) District - drop-down of
	current BST Districts for the
	selected State defaulted to
	user's District
	Type - drop-down of valid
	SCID type codes &
	descriptions from LOV_SCID_TYPE
	table
	Upon selection of the above,
	the system can select the next
	available SCID for assignment
	(see SCID assignment) and
	present the SCID to the user.
	The user can then optionally enter:
	1) LEG Installation ID
	,
	2) Equipment
	3) Authorization Number
	4) Address
	5) Service Date
	Upon selecting
	an "ASGN SCID" button,
	the SCID can be assigned. Upon
	assignment the ASGN SCID button can
	change to UPDATE SCID. The user
	may update any of the 5 optional
	items and hit the UPDATE SCID
	button to save the changes. (Note:
	Once assigned, the State, District,
	Type codes may not be changed.)

### SCID Assignment:

FMT can create a new SCID by:

Select from SCID\_Log any SCID with a first character, second, third and last characters matching user selection and SCID assignment rules:

- 1) status of New. If found, use this SCID. If none found
- 2) status of Unassigned and a Status Date where 'today' minus Status Date in days is greater than LOV\_ FMT\_PARAMS: SCID\_Unasgn\_Age. If found, use this SCID. If none found then,
- 3) status of Deleted and a Status Date where 'today' minus 60 Status Date in days is greater than LOV\_FMT-\_PARAMS: SCID\_Deleted\_Age. If found, use this SCID. If none found then,
- 4) assign a new SCID:

A new SCID is formed by concatenating SCID\_ 65 First\_Char+SCID\_Second\_Char+SCID\_Third\_Char+(SCI-D\_ASGN: SCID\_Num+1)+SCID\_Last\_Char

50

Using SCID assignment rules (see logical data model embodiments).

The FMT system may assign a new SCID "on the fly" or develop a batch process to add new SCID to the log on a periodic basis (ADD SCID function).

SCID Log Tool—VIEW SCID LOG

10	Embodiment	Display SCID Data From Log Based On User Specified Attributes
	Description	User can select for display the SCID log data by using various
		filters.
		State; District; Equipment;
15		Status.
	Data	See Logical Data Model
		Embodiments for SCID_LOG.

#### SCID Log Tool—UNASGN SCID

20	2012 208 1001	
	Embodiment	Change The Status On A SCID
		From Assigned To Unassigned
25	Description	User can input a SCID or select a SCID from a generated list of SCIDs with Status =
		Assigned created by the current user.  Data for the SCID is displayed
		on the screen and a UNASGN Button allows the user to
30		Unassign. System changes Status to 'U' for unassigned and records the date. The Unassign
		function can only be performed by the user that Assigned the
35	Data	SCID. N/A

#### SCID Log Tool—UPDATE SCID LOG

0	Embodiment	A Process To Update SCIDs in the SCID Log
	Description	This process can periodically update the SCID status in the
		SCID Log. This may require a comparison of SCIDs actually
5		in FMT and the Log. For SCID
		in the Log with a Status of Working that are not found in
		FMT, the status is updated to
		Deleted. For SCIDs that are
0		found in FMT, then status is updated to Working.
U	Data	SCID Log Status

6.2.8.6 Enhance Existing Database, Posting & Viewing Tools

Embodiment	Enhance the existing OPEDS Facility Management database, posting &
	viewing tools
Description	The system can support additional fiber functionality: Inter-wire center connector, fiber splice feature, graphical location of fiber in Under- ground records, and CSA/Equipment Location features.

51 -continued

# 52 -continued

facility FMT: COMP loaded COND DRAW FOREI only) T FIBER MANF *** Equ create ! area # ! MX: se POLE: TERM table): XCON ROUT ROUT FIBER	: all IOLE: all 4c & 45c ipment Location**: for each unique in MX te above for reference
---	--

## 6.2.8.7 Develop Tools to Populate the Facility Data Enhancements

Embodiment	Develop tools to populate the facility data enhancements
Description	Develop tools to automatically populate the facility data enhancements and to provide manual effort to populate remaining data that cannot be accomplished mechanically

## 6.2.8.8 Develop Tools to Add Existing Fiber and CSA Locations

Embodiment	DEVELOP TOOLS TO ADD EXISTING FIBER AND CSA LOCATIONS AUTOMATICALLY/ MANUALLY
Description	Develop tools to add existing fiber and CSA locations, along with key structure and connectivity
Spatial Embodiment	features/attributes to the FMT SDO Database, both automatically from OPEDS converted wire centers, and manually for non-OPEDS converted wire centers. Provide capability to place 'planned existing <feature>' whenever necessary in add- ition to creating from OPEDS data via SDL. SDL creates Equipment Locations from MX data (see note above in 6.2.8.6)</feature>

If no western state fiber conversion is going to take place, additional scripts can be required to allow users to import ArcView files.

6.2.8.9 Allow User to Perform Fiber Traces

Embodiment	Allow user to perform fiber	
Description	traces The user should be able to perform a trace to a fiber by	65

entering a given attribute or criteria for the fiber.

Spatial Embodiment Multiple trace functions are available to user via selection from physical sheath or user input. Route trace, highlight route, diversity check, fiber cut location, etc.

## 6.3 Planning Layer Functionality6.3.1 LRS Overview

Planning may occur in many fashions and by many names. In order to avoid confusion, this document may use some new terms to describe the planning process.

The basic planning unit is the Location Relief Strategy (LRS). When creating a LRS, the resource planning system may automatically create or allow the user to select an existing planning Need. Multiple Alternative LRSs may be created for one Need. While many alternative relief strategies may or may not exist, according to some embodiments of the present invention, only of the LRSs is defined as a primary LRS for a need, with one or more of the other LRSs defined as alternate LRSs for the need. A LRS may be related to one or more Point Of Interest (POI). LRSs may be grouped into a View. FIG. 9 demonstrates the relationship between these concepts.

A POI is a particular location where a need exists or is predicted. POI is a geographic location, which may be a point, a polygon, or a group of noncontiguous points and/or polygons. For example, an existing building needs additional fiber capacity or a customer purchases a service, which requires diversification.

A LRS describes a means of fulfilling a need at one or more particular POIs at a given time. For example, a LRS may call for placing 2000 ft of 48-strand fiber or for the rearranging of existing fiber splices. Whenever an alternative LRS exists, one of the LRS's can be designated as Primary. By default, when a search is executed, only those LRS's, which are designated as Primary, are to be considered for the search.

A View is a collection of Primary LRS's (by default, but a View may be a collection of Primary or Alternative LRS's with an override). Examples of Views could include a three year construction plan View, a route View, a wire center View, etc. Headquarters staff can have the ability to create default View definitions, but individual users can also have the ability to create View definitions.

FIG. 10 describes in detail the functions of LRS within FMT.

6.3.1.1 LRS States

55

60

-		
_	State	Definition
;	PRIVATE	A LRS is initially created in the Private state. Only the creator or a super-user can see it and modify a LRS in this state.
	PUBLISH	In this state, all users can see the LRS in a Tabular list and in Spatial views. Any user with update permission can view, select, and modify it. Any user without
)		update permission can view the LRS and add a LRS Note, but can not modify the LRS. Any LRS (primary or alternate) can be published from the Private state. Un-Publish a LRS and change a Publish LRS back to Private state.
i	DELETE	Any user with update permission may delete a LRS from the Publish state. A LRS in this state does not appear in

selected LRS.

## 54 6.3.1.2 Primary LRS State Transitions

State	Definition		From			
	normal Tabular list or Spatial views. Any user with update permission may select	5	From State	To State	Action	Notes
	a view of Deleted LRS from the previous Publish state and may select and clone		<null></null>	Private	User: LRS Create	The LRS Create function creates a LRS in the Private state.
	or Undelete a Deleted LRS (back to Publish state). Only the LRS creator or a super-user can view Deleted LRS from	10	Private	Publish	User: LRS Publish	The LRS Publish function can change a LRS to the
	the previous Private state and may select and clone or Undelete a Deleted LRS	10	Publish	Private	User: LRS	Publish state.  The LRS Un-Publish function can change an LRS to the
	(back to Private state). An Alternate LRS with the Primary LRS in Design state				Un-Publish	Private state from the Publish state.
	can not be Undeleted. A LRS can not be		Private or	Delete	User:	The LRS Delete function can
DESIGN	modified in the Delete state.  When a user elects to hand-off the LRS to PMTool, the LRS State changes to	15	Publish		LRS Delete	change an LRS to the Delete state from the Private or Publish states.
	Design upon successful hand-off. Only a Primary LRS may be handed-off. All		Delete	Private or Publish	User: LRS	The LRS Undelete function can change an LRS to its
	users can see the Design state LRS in Tabular list and Spatial views. Any user	20			Undelete	previous state (Private or Publish) from the Delete
	with update permission can view, select, and modify it. Modification can trigger a					state. An Alternate LRS with the Primary LRS in
	PM Tool update. Any user without update permission can view the LRS and add					Design state can not be Undeleted.
	a LRS Note, but can not modify the LRS. Once a LRS is in the Design state, it	25	Delete	<null></null>	System: LRS Purge	The system LRS Purge function or user LRS
	can no longer be deleted, but it may be canceled.				User: LRS Purge	Purge Deleted function can completely remove a LRS in
CANCEL	Only a LRS in Design state may be				Deleted	the Delete state from the FMT system.
	canceled. Any user with update permission may cancel a LRS. A LRS in this state		Publish	Design	User: LRS Hand-off	The LRS Hand-off function can change an LRS to the
	does not appear in normal Tabular list or Spatial views. Any user with update	30			LKS Hand-on	Design state from the
	permission may select a view of Canceled					Publish state if successfully handed-off
	LRS and may select and Restore a Can- celed LRS back to the Design state. A		Dagian	Canaal	User:	to PM Tool. The LRS Cancel function car
COMPLETE	LRS can not be modified in the Cancel state.  When the authorization associated with	35	Design	Cancel	LRS Cancel	change an LRS to the Cancel
	the PMTool task is completed, FMT can complete the LRS. In the Complete state		Cancel	Design	User:	state from the Design state.  The LRS Restore function ca
	all users can see the LRS in a Tabular list and in Spatial views. The LRS may				LRS Restore	change an LRS to the Design state from the Cancel state.
	no longer be modified. A user with	40	Cancel	Archive	System: LRS Archive	The LRS Archive function ca change an LRS to the Archive
	update permission may select the LRS for cloning.	40			User: LRS Archive	state from the Cancel state. This function can be
ARCHIVE	Any user may add a LRS Note.  The FMT system can automatically archive a LRS 'x' days after the LRS is					automatically initiated by the FMT system or may be
	completed. This value can be set in a FMT Parameters table. A user with update	45	Design	Complete	System:	user initiated. The system LRS Complete
	permission may manually archive the LRS.  In the Archive state, the amount of				LRS Complete	function can change an LRS to the Complete state from
	information associated with the LRS is reduced and can not be undone. The LRS					the Design state when the authorization is shown
	may no longer be modified. A user with	50	Complete	Archive	System:	as closed in PMTool. The LRS Archive function
	update permission may select, via a View Archive function, the LRS for view		1		LRS Archive User:	can change an LRS to the Archive state from the
	and cloning. LRS Notes can no longer be added.				LRS Archive	Complete state. This function can be
<null></null>	The FMT system can automatically purge a LRS 'x' days after the LRS is	55				automatically initiated by the FMT system or may be
	archived or deleted. The number of days can be set in a FMT Parameters table,		Archive	<null></null>	System:	user initiated. The system LRS Purge can
	and can be different entries for Archive Purge and Deleted Purge. Any user with				LRS Purge	completely remove a LRS in the Archive state from
	update permission may select a view of	60				the FMT system.
	Deleted LRS from previous state of Publish and may select and Purge a Deleted					
	LRS. Only the creator or super-user may select a view of Deleted LRS from			3 Alternat		1 6 2 6 25
	previous state of Private and Purge a		FIG. 1 LRS.	i i describ	oes in detail t	he functions of an Alter

65 LRS.

Alternate LRS State definitions are the same as Primary, but are limited to Private, Publish, and Delete.

## 6.3.1.4 Alternate LRS State Transitions

To State	Action	Notes	5		embodiments of the present invention, more than one LRS
Private	User: LRS Create	The LRS Create function creates a LRS in the Private state.		Spatial Embodiment	may be defined as a primary LRS for a need. <need <="" and="" initiated="" is="" lrs="" td=""></need>
Publish	User: LRS Publish	The LRS Publish function can change an	10		created in FAS. LRS creation in Spatial is instigated by a call from FAS (LRS cannot
Private	User: LRS Un-Publish	The LRS Un-Publish function can change an LRS to the Private state from the			be created within Spatial; it is first be created in FAS)> there is a function in FAS that allows user to kick
Delete	User: LRS Delete	The LRS Delete function can change an LRS to the Delete state from the Private or Publish states. Also the LRS Hand-off function can change all Alternate associated LRS to Delete.	15 20	Spatial to FAS <i>VF</i> Scenario:	off Spatial to create a LRS in spatial; FAS passes us needed admin info (unique id, user, etc.) to create new 'folder' in our tree view. User identifies point(s) of interest, etc. Launch FAS' 'Create LRS web page';
Private or Publish	User: LRS Undelete	The LRS Undelete function can change an LRS to its previous state (Private or Publish) from the Delete state. An	25	FAS web page opens and	n Spatial and selects "Create LRS" l user creates new LRS d be displayed on the FAS screen:
<null></null>	System: LRS Purge User: LRS Purge Deleted	Alternate LRS with the Primary LRS in Design state can not be Undeleted. The system LRS Purge function or user LRS Purge Deleted function can completely remove a LRS in the Delete	30	(x,y in feet), Easement C Restrictions, Power Emb Strand, Fiber Connectors Contact, Contact Info, Tr LecIII interface, All PM	ss, CLLI, GLC, Easement_ID, Easement Size omments, Text of Easement and odiments, Point(s) of Interest, Fiber, Service Date, Customer Name, Customer rigger, Prog Codes, All LecIII data in Tool data in PM Tool interface, All Interface, Xbox(s) associated with LRS, Xbox
	Private  Publish  Private  Delete  Private or Publish	Private User: LRS Create  Publish User: LRS Publish  Private User: LRS Un-Publish  Delete User: LRS Delete  Private or User: Publish LRS Undelete <null> System: LRS Purge User: LRS Purge User: LRS Purge User: LRS Purge</null>	Private User: The LRS Create function the Private state.  Publish User: The LRS Publish function can change an LRS to the Publish state.  Private User: The LRS Un-Publish function can change an LRS to the Private state from the Publish state.  Delete User: The LRS Delete function can change an LRS to the Delete state from the Publish state.  Delete User: The LRS Delete function can change an LRS to the Delete state from the Private or Publish states. Also the LRS Hand-off function can change all Alternate associated LRS to Delete.  Private or User: The LRS Undelete function can change all LRS to its previous state (Private or Publish) from the Delete state. An Alternate LRS with the Primary LRS in Design state can not be Undeleted. <null> System: The System LRS Purge function or user LRS Purge   <null> System: LRS Purge function or user LRS Purge   LRS Purge function can completely</null></null>	Private User: The LRS Create function creates a LRS in the Private state.  Publish User: The LRS Publish function LRS Publish Can change an LRS to the Publish state.  Private User: The LRS Un-Publish function can change an LRS to the Private state from the Publish state.  Delete User: The LRS Delete function 15 LRS Delete Can change an LRS to the Private state from the Publish state.  Delete User: The LRS Delete function 15 LRS Delete Can change an LRS to the Delete state from the Private or Publish states. Also the LRS Hand-off function can change all Alternate associated LRS to Delete.  Private or User: The LRS Undelete function can change an LRS to its previous state (Private or Publish) from the Delete state. An Alternate LRS with the Primary LRS in Design state can not be Undeleted.    Alternate LRS Purge   Can Change Deleted	Private User: The LRS Create function LRS Create creates a LRS in the Private state.  Publish User: The LRS Publish function LRS Publish can change an LRS to the Publish state.  Private User: The LRS Un-Publish LRS function can change Un-Publish an LRS to the Private state from the Publish state.  Delete User: The LRS Delete function LRS Delete Can change an LRS to the Delete state from the Private or Publish states. Also the LRS Hand-off function can change all Alternate associated LRS to Delete.  Private or User: The LRS Undelete function Publish LRS Undelete Crivate or Publish) from the Delete state. An Alternate LRS with the Primary LRS in Design state can not be Undeleted.    Alternate LRS Purge function or user LRS Purge function can completely Deleted remove a LRS in the Delete   LRS Purge function can completely Deleted remove a LRS in the Delete   LRS Purge function can completely Deleted remove a LRS in the Delete   LRS Purge function can completely Deleted remove a LRS in the Delete   LRS Purge function can completely Deleted remove a LRS in the Delete remove a LRS in the D

## 6.3.2 Provide Location Relief Strategy Administration

### 6.3.2.1 Create a LRS and Associated Administrative Data

## 6.3.2.2 Create Alternative LRS and Associate for a Route

		40		
Embodiment	Provide User with the ability to create a LRS and associated administrative data		Embodiment	Provide User with the ability to create an alternative Location Relief Strategy
Description	User should be able to create a Location Relief Strategy using the tools available. In order to create a LRS, the user should have set some sort of location - a start and an end point.	45	Description	associated for a route. Users should be able to create an alternative LRS for a particular route. This is can be as a fallback or just an alternative for a route. The user can set the main LRS as
	A user should also be able to create administrative data to go along with the LRS. This administrative data can be such things as creator name, creation date of an LRS, last	50		primary if he/she wants and the second or third as alternatives. At least one of the LRS created by the user must be a Primary; any others created would be alternative.
	modified date, status type,		Data	See Data Embodiments: LRS &
Data	etc. See Data Embodiments: LRS & Hand-Off Package	55	Scope for FAS:	Hand-Off Package
General Discussion	LRS overview - new concept/ feature called NEED. This is the highest level of LRS		Manage creation of a Alternative statuses Scenario:	lternative LRS and changing of Primary and
	hierarchy. A NEED may be satisfied by one or more LRSs. An LRS may have one or more solutions. However, according to some embodiments of the present invention,	60	User selects "Create user wants to clone a created using all of the	a LRS user decides to create an alternative. Alternative LRS" link. The system asks if the n existing LRS. User selects Yes. A new LRS is he same data as the selected LRS. hould be displayed on the FAS screen:
	only one LRS may be defined as a primary LRS, and all other LRSs are defined as	65	Same data as Primary	y LRS

## 6.3.2.3 Modify LRS Administrative Data

## 58

## -continued

			Users	Loop Capacity Mangers,
Embodiment	Provide the appropriate user	(		Long Term Planners,
	the ability to modify the	5		Infrastructure IOF Planners.
	administrative data of a LRS.	5	Scope for FAS:	
Description	Administrative Data includes	,	Managa gaarahing of LDS bac	and an tabular data: dignley I BS upon
•	data such as date LRS was		Manage searching of LKS bas equest from Spati	sed on tabular data; display LRS upon
	created, status of LRS,		Scenario:	
	creator, etc. It may include	10		
	all data that can be admin-			on key word. A list of matching LRS's
	istered about the LRS, except			ired LRS, LRS screen is displayed.
	for the LRS itself.	1	Data elements that should be	displayed on the FAS screen:
	The user who created the LRS,		Same as Primary LRS.	
	the user's alternative,	15	Same as I filliary ERG.	
	and/or a super user have			
	permissions to modify the		6.3.2.5 Logically De	elete LRS and Associated Data
	administrative data of a			
	LRS. A user is able to modify an	20 -		
	LRS till the handoff state.	20	Embodiment	Logically Delete LRS and
Data	See Data Embodiments: LRS &		Description	Associate Data User should be able to delete
	Hand-Off Package		резенрион	a LRS and it's associated
Scenario:	wownge			administrative data, which
				can logically perform a delete.
.RS decides to modify	existing LRS. User selects "Modify LRS"	23		The only users allowed to do this are the creators of the
	e no longer write protected and user can			LRS, its alternate, and a
nodify and then save.	. To rouger write protected and user can			super user. The data can be
•	uld be displayed on the FAS screen:			deleted from the user's perspective, but can remain in
zata cicinents that shot	und be displayed on the 1745 sereen.	30		storage until purged.
				User can decide to delete
Same as Drimam, I DC				
Same as Primary LRS				LRS from either Spatial or FAS
Same as Primary LRS				Web; upon deletion in one
	d Patriava LPS and Administrativa Da	enta.		
	d Retrieve LRS and Administrative Da	nta 35	Users	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers,
	d Retrieve LRS and Administrative Da	nta 35	Users	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners,
6.3.2.4 Save and	d Retrieve LRS and Administrative Da	ata 35		Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners.
6.3.2.4 Save and	Provide user with the ability to save and retrieve LRS	nta 35	Users  Spatial Embodiment	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy).	ata 35		Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS.
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS	ata 35		Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy).	35		Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS.
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a	35		Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later	35		Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions.	35		Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case,
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later	35		Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish"	35		Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as	35	Spatial Embodiment	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes	35		Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes	40	Spatial Embodiment	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the	35	Spatial Embodiment  Scope for FAS:	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the	40	Scope for FAS:  Manage the LRS lifecyclescenario:	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the	40	Scope for FAS:  Manage the LRS lifecycl Scenario:  User decides that a partic	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.  le.
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the administrators, so that they can	40	Scope for FAS:  Manage the LRS lifecycl Scenario:  User decides that a partic	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the administrators, so that they can help with support issues. This is provided only if a minimal amount of information	40	Scope for FAS:  Manage the LRS lifecycl Scenario:  User decides that a partic	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.  le.
6.3.2.4 Save an	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the administrators, so that they can help with support issues. This is provided only if a minimal amount of information (such as POI (point of	40	Scope for FAS:  Manage the LRS lifecycl Scenario:  User decides that a partic	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.  le. cular LRS is not required and should be ete; LRS is changed to the Deleted state.
6.3.2.4 Save and imbodiment Description	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the administrators, so that they can help with support issues. This is provided only if a minimal amount of information (such as POI (point of interest)) has been entered.	40 45 50	Scope for FAS:  Manage the LRS lifecycl Scenario:  User decides that a partic deleted; User selects deleted	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.  le. cular LRS is not required and should be ete; LRS is changed to the Deleted state.
6.3.2.4 Save and mbodiment Description	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the administrators, so that they can help with support issues. This is provided only if a minimal amount of information (such as POI (point of	40 45 50	Scope for FAS:  Manage the LRS lifecycl Scenario:  User decides that a partic deleted; User selects deleted	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.  le. cular LRS is not required and should be ete; LRS is changed to the Deleted state.
6.3.2.4 Save and imbodiment Description	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the administrators, so that they can help with support issues. This is provided only if a minimal amount of information (such as POI (point of interest)) has been entered. See Data Embodiments: LRS & Hand-Off Package At a user's request, FMT can	40 45 50	Scope for FAS:  Scope for FAS:  Manage the LRS lifecycles Scenario:  User decides that a particular deleted; User selects deleted; User selects deleted; Embodiment	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.  le.  cular LRS is not required and should be ete; LRS is changed to the Deleted state.  Purge LRS and Associated Data
6.3.2.4 Save and Embodiment Description	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the administrators, so that they can help with support issues. This is provided only if a minimal amount of information (such as POI (point of interest)) has been entered. See Data Embodiments: LRS & Hand-Off Package At a user's request, FMT can save the current LRS within	40 45 50	Scope for FAS:  Scope for FAS:  Manage the LRS lifecycles Scenario:  User decides that a partic deleted; User selects deleted; User Scenario:  6.3.2.6 Purge LRS at	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.  le.  cular LRS is not required and should be ete; LRS is changed to the Deleted state.  Purge LRS and Associated Data  Purge LRS and Associated Data LRS and their associated data
6.3.2.4 Save and Embodiment Description	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the administrators, so that they can help with support issues. This is provided only if a minimal amount of information (such as POI (point of interest)) has been entered. See Data Embodiments: LRS & Hand-Off Package At a user's request, FMT can save the current LRS within its database. Users can	40 45 50	Scope for FAS:  Scope for FAS:  Manage the LRS lifecycles Scenario:  User decides that a particular deleted; User selects deleted; User selects deleted; Embodiment	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.  le.  cular LRS is not required and should be ete; LRS is changed to the Deleted state.  nd Associated Data  Purge LRS and Associated Data LRS and their associated delete flag
6.3.2.4 Save and imbodiment Description	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the administrators, so that they can help with support issues. This is provided only if a minimal amount of information (such as POI (point of interest)) has been entered. See Data Embodiments: LRS & Hand-Off Package At a user's request, FMT can save the current LRS within	40 45 50 55	Scope for FAS:  Scope for FAS:  Manage the LRS lifecycles Scenario:  User decides that a particular deleted; User selects deleted; User selects deleted; Embodiment	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.  le.  cular LRS is not required and should be ete; LRS is changed to the Deleted state.  Purge LRS and Associated Data  Purge LRS and Associated Data LRS and their associated data
6.3.2.4 Save and Embodiment Description	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the administrators, so that they can help with support issues. This is provided only if a minimal amount of information (such as POI (point of interest)) has been entered. See Data Embodiments: LRS & Hand-Off Package At a user's request, FMT can save the current LRS within its database. Users can retrieve a LRS based on search criteria or from a list.	40 45 50 55	Scope for FAS:  Scope for FAS:  Manage the LRS lifecycles Scenario:  User decides that a particular deleted; User selects deleted; User selects deleted; Embodiment	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.  le.  LIFE SIS INDITIONAL STATE OF SPATIAL STATE O
6.3.2.4 Save and Embodiment Description	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the administrators, so that they can help with support issues. This is provided only if a minimal amount of information (such as POI (point of interest)) has been entered. See Data Embodiments: LRS & Hand-Off Package At a user's request, FMT can save the current LRS within its database. Users can retrieve a LRS based on search criteria or from a list. FMT can also provide the ability to retrieve the saved LRS by	40 45 50 55	Scope for FAS:  Manage the LRS lifecycl Scenario:  User decides that a partic deleted; User selects deleted:  6.3.2.6 Purge LRS at Embodiment Description	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.  le.  cular LRS is not required and should be ete; LRS is changed to the Deleted state.  Purge LRS and Associated Data LRS and their associated data can have a logical delete flag associated with them so that a corporate purge process can purge periodically based on a BST defined criteria.
6.3.2.4 Save and Embodiment Description	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the administrators, so that they can help with support issues. This is provided only if a minimal amount of information (such as POI (point of interest)) has been entered. See Data Embodiments: LRS & Hand-Off Package At a user's request, FMT can save the current LRS within its database. Users can retrieve a LRS based on search criteria or from a list. FMT can also provide the ability to retrieve the saved LRS by selecting the file name from a	40 45 50 55	Scope for FAS:  Scope for FAS:  Manage the LRS lifecycles Scenario:  User decides that a particular deleted; User selects deleted; User selects deleted; Embodiment	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.  le.  cular LRS is not required and should be ete; LRS is changed to the Deleted state.  nd Associated Data  Purge LRS and Associated Data LRS and their associated data can have a logical delete flag associated with them so that a corporate purge process can purge periodically based on a BST defined criteria. Existing Location Relief
	Provide user with the ability to save and retrieve LRS (Location Relief Strategy). User can save unfinished LRS and retrieve them when needed. The users who have permission set can save a LRS and retrieve it later to make changes or additions. Once the user has created a LRS, he/she can have the option to "publish" proposed routes or maintain it as "private". Published routes are available for viewing by other FMT users. Private routes are only available to the owner/author as well as the administrators, so that they can help with support issues. This is provided only if a minimal amount of information (such as POI (point of interest)) has been entered. See Data Embodiments: LRS & Hand-Off Package At a user's request, FMT can save the current LRS within its database. Users can retrieve a LRS based on search criteria or from a list. FMT can also provide the ability to retrieve the saved LRS by	40 45 50 55	Scope for FAS:  Manage the LRS lifecycl Scenario:  User decides that a partic deleted; User selects deleted:  6.3.2.6 Purge LRS at Embodiment Description	Web; upon deletion in one application the LRS is deleted from the other. Loop Capacity Mangers, Long Term Planners, Infrastructure IOF Planners. Logical delete is supported. Life cycle closures, i.e., via PMTool, is managed by FAS. FAS sends update to Spatial to logically delete LRS/data. Manual deletes, i.e., deleted by a user, can be performed in either FAS or Spatial (PLEASE CONFIRM). In this case, system in which the delete is initiated sends update to the other system to perform logical delete of LRS/data.  le.  cular LRS is not required and should be ete; LRS is changed to the Deleted state.  Purge LRS and Associated Data LRS and their associated data can have a logical delete flag associated with them so that a corporate purge process can purge periodically based on a BST defined criteria.

	-continued			6.3.2.9 Close an	LRS Manually	
notifies Spatial to Purge (physically delete) LRS/data. Scope for FAS:		<b>-</b> - 5	Embodiment Description	Close an LRS Manually User can be able to		
Manage the LI Scenario:	RS lifecycle.			Scope for FAS:	close an LRS manually	
After an LRS l	nas been in the Archive state fo	or 'x' days it can	10	Manage LRS Life Cycle Scenario:	e	
6.3.2.7 Creat	e, Modify, and Delete L	RS Notes by User	15	enter the closed state (fo	anded off the user decided that the LRS should or example, there is no EWO for the LRS).  d is no longer shown as an active LRS.	
Embodiment  Description	Create, Modify, and D LRS Notes by User User can create, modif and delete LRS notes.	îy, The LRS		6.3.2.10 Alert C	overage Service Dates on LRS	
	can go through the pro of create, publish/un p handoff, complete, del and purge. Once an LRS has been	ublish, ete, ı published	20	Embodiment Description	Alert Overage Service Dates on LRS User can be provided with an alert of overage LRS x days after planned service date	
	any user with access to FMT can create and ac Notes. LRS notes can	dd LRS not be	25	Data Data I	Source (Primary, Description Secondary)	
	deleted; as a user adds note, the user's name,			Scope for FAS:		
	date/time stamp are red A LRS note should be in the FAS LRS screen	viewable	<b>–</b> 30	Modify the Main Screen notification for Overage		
Data	Source (Primary, Data Description Secondary)		<b>-</b> 30	Scenario:  LRS has a service date of X. On day X + 30 the creator of the LRS logs into FMT and finds an alert that there is an overage LRS.		
User Name User ID Date/Time Comment	User's First, Middle, and Last Name UID Date Long text	Siteminder Siteminder System User	35	The user selects the link LRS. The user then mod longer overage.	at to the list of overage LRS's and selects the diffies the service date so that the LRS is no all be displayed on the FAS screen:	
Scope for FAS		CSCI	-		x, Location(s), Xbox(s), Service Date elements for this embodiment:	
Allow user to o	create LRS notes.		40	FAS		
	RS. User selects "Add LRS No ation.	ote" and enters	_	6.3.2.11 Depend	dent LRS Clone	
6.3.2.8 Provi	de LRS Reports by Use	er Selection Filters	45	Embodiment Description	Dependent LRS Clone User can build a new LRS upon one or more LRS's. The	
mbodiment	Provide LRS Reports b Selection Filters	oy User	-		status of the facilities which are proposed in the preceding LRS's is changed to "proposed	
escription	User can filter out and a particular LRS or see one using filters that sl what they would like t	arch for how	50		existing." The tabular data includes links to the LRS's on which this LRS is dependent. When a new LRS is	
ata C. E. C	See Data Embodiment				cloned from another LRS	
elds, should be sea e user should expl	h for LRS based on key words. archable. To search for deleted licitly specify that the search si e LRS's are displayed with mir	and canceled LRS's hould include	- 55	Spatial Embodiment	on which it is to be dependent, all data is copied, and it is the user's responsibility to choose which data should be deleted. When a user is viewing a LRS,	
	or cannot see any additional da		<b>–</b> 60	Бранаі Енівоцінісій	when a user is viewing a LKS, the facilities on which it is dependent are shown as "proposed existing"	

User selects LRS search screen. User enters search criteria. A list of LRS's is displayed.

Data elements that should be displayed on the FAS screen:

LRS ID, Scope of Work, Location(s), Xbox(s), Primary/Alternative, Service Date, Trigger, LRS status (published, handed off, etc.)

Manage LRS cloning and dependent LRS links. Scenario:

Scope for FAS:

 $^{65}$   $\,$  User selects LRS and selects "create clone". User then opens cloned LRS and enters other LRS's on which it is dependent. FAS

20

55

60

65

## 62

-continu	$\rho$ 0

shows these LRS's, along with their service dates, in the LRS screens	-
Data elements that should be displayed on the FAS screen:	5
Precading I PS's and service dates	-

## 6.3.3 Provide Graphical and Tabular Planning Tools

FAS

Source for all the data elements which are required for this embodiment:

# 6.3.3.1 Generate LRS Schematics from Existing Fiber $_{\rm 15}$ Data

Embodiment	Provide user the ability to generate a LRS schematic
Description	from existing fiber data Using the graphical tools
	in FMT, users with the appropriate permissions
	can generate a LRS schematic
	from existing fiber data
~	storage.
Spatial Embodiment	View that contains only data associate with (to) an LRS.
Embodiment	Provide drawing tools and
Emodument	symbols to denote all
	necessary equipment and
	facility items within the
	Location Relief Strategy
B 1.4	(LRS).
Description	Symbols can be consistent with existing .DGN and .LND
	symbology.
Data	See Data Embodiments: LRS &
	Hand-Off Package
System Behavior	Users can have a palette of
	symbols that represent facilities
	and landbase features to select from in order to draw a LRS
Users	for future fiber optic routes.  Loop Capacity Mangers, Long
03613	Term Planners, IOF
	Planners.
Spatial Embodiment	Provide placement of planned &
•	planned existing features,
	complements, annotation, etc.
	Attribution of features can
	be possible but not enforced or
	validated.

## 6.3.3.2 Provide Drawing Tools, Symbols, and Attribute 50

Creation Functions

Embodiment	Provide drawing tools and symbols to denote all
	necessary equipment and facility items within the
	Location Relief Strategy (LRS).
Description	Sybols can be consistent with existing .DGN and .LND symbology.
Data	See Data Embodiments: LRS & Hand-Off Package
System	Users can have a palette of symbols that represent
Behavior	facilities and landbase features to select from in
	order to draw a LRS for future fiber optic routes.
Users	Loop Capacity Managers, Long Term Planners, IOF
	Planners.
Spatial	Provide placement of planned & planned existing
Embodiment	features, complements, annotation, etc.
	Attribution of features can be possible but not
	enforced or validated.

## 6.3.3.3 Document Future Location Relief Strategy, and/or DLE locations

En	nbodiment	Provide users with the
		ability to document Location
		Relief Strategy and/or
		DLE equipment.
De	escription	The user can have an option
		to draw/document a future
		fiber route and DLE equip-
		ment using tools provided in
		FMT. Users can also either
		set each LRS as private or
		publish them.
Da	ata	See Data Embodiments: LRS &
		Hand-Off Package
Sy	stem behavior	Users can have a variety of
		tools to select from and can
		document and/or draw a future
		LRS, depending on user
		permissions.
Us	sers	Loop Capacity Mangers, Long
		Term Planners, IOF Planners.

#### 6.3.3.4 Retrieve and Display LRS

Embodiment	Provide users with the ability
	to retrieve LRS with a
	user- defined job description
	and display on screen.
Description	The user can have the option to
	"publish" LRS or maintain
	it as "private." Published
	routes are available for
	retrieving and displaying on
	screen by other FMT users. Private
	routes are only available to
	the owner/author.
Data	See Data Embodiments: LRS &
	Hand-Off Package
System Behavior	FMT can also provide the ability
	to retrieve or search for a
	LRS from its database or from
	a list. This data is corporate
	data and should be stored in
	corporate server.
Users	Loop Capacity Mangers, Long
	Term Planners, IOF
	Planners.

## 6.3.3.5 Display Multiple LRS Graphically

Embodiment	Provide users with the ability to retrieve multiple LRS with a user- defined job description and display them on screen.
Description	Users can display multiple LRS at one time in order to compare more than one at a time, etc.
Data	See Data Embodiments: LRS & Hand-Off Package
System Behavior	FMT can also provide the ability to retrieve or search for a LRS from its database or from a list. After selecting the LRS desired, FMT can retrieve the LRS and display it on screen. The user can select another LRS or search for another in order to view more than one at a time. This data is corporate data and should be stored in corporate server.

-continued

### 6.3.3.8 Publish LRS

64

	-continued			
Users	Loop Capacity Mangers, Long Term Planners, IOF		mbodiment	Provide users the ability to
Spatial Embodiment	Planners. User can select one or more	5	modificat	publish a LRS in order for other users to view and add
Space Emocamen	LRS to view. User desires to be able to	D	Description (	comments, etc. Users with appropriate per-
	visually distinguish one LRS	D	rescription	missions can publish a LRS they have created in order for
	from another. User can link from facilities	10		other users to view and add
	associated with one LRS and see the details in FAS			comments and suggestions to them.
				The original user who created the LRS has the option of
6.3.3.6 Copy Existing	g LRS to New LRS	15		publishing the LRS (for everyone to view) or making it private (for no one to view)
Embodiment	Provide user with the ability	D	<b>D</b> ata	See Data Embodiments: LRS & Hand-Off Package
	to copy an existing LRS into a new LRS.		ystem Behavior	Users view a LRS that have
Description	**Described above** Users can take a previous LRS	20		been set to publish through FMT and its on-screen
	already created within FMT and copy it to a new LRS in	U	Jsers	interface. Loop Capacity Mangers,
	order to use it further or make additions/changes.	25		Long Term Planners, IOF Planners.
	This copy can be used as a brand new LRS, as an	<sup>25</sup> <u>s</u>	cope for FAS:	
	alternative to the original in addition to the original, or converted to "assumed		Manage LRS life cycle cenario:	
Data	existing" for a new LRS. See Data Embodiments: LRS & Hand-Off Package		*	which he is the owner. User selects
			donai ERD and ERD is i	
System Behavior	The system can take the original LRS and copy it to a new	$\frac{\mathrm{D}}{\mathrm{D}}$	Pata elements that should be	e displayed on the FAS screen:
System Behavior Users	LRS and copy it to a new page. Loop Capacity Mangers, Long	L S	RS details	
	LRS and copy it to a new page.	35 <u>S</u>	RS details	ents which are required for this embodiment:
Users	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF	35 <u>S</u>	RS details ource for all the data eleme	
	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF	35 <u>S</u>	RS details ource for all the data eleme	ents which are required for this embodiment:
Users	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners	35 <u>S</u>	RS details ource for all the data elements AS 6.3.3.9 View LRS a	ents which are required for this embodiment:  nd DLE Plans
Users 6.3.3.7 Modify LRS	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners  Provide user with the ability to modify a proposed LRS Only creators/designers can	35 <u>S</u>	RS details ource for all the data eleme AS 6.3.3.9 View LRS a Embodiment	ents which are required for this embodiment:  nd DLE Plans  Provide users the ability to view a LRS and DLE
Users  6.3.3.7 Modify LRS  Embodiment	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners  Provide user with the ability to modify a proposed LRS Only creators/designers can modify LRS. In addition, FMT can store an audit trail	35 <u>S</u>	RS details ource for all the data elements AS 6.3.3.9 View LRS a	ents which are required for this embodiment:  nd DLE Plans  Provide users the ability to view a LRS and DLE Same as embodiment See Data Embodiments: LRS
Users  6.3.3.7 Modify LRS  Embodiment	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners  Provide user with the ability to modify a proposed LRS Only creators/designers can modify LRS. In addition, FMT can store an audit trail of modifications to each LRS. See Data Embodiments: LRS &	35 E	RS details ource for all the data eleme AS 6.3.3.9 View LRS a Embodiment Description	ents which are required for this embodiment:  nd DLE Plans  Provide users the ability to view a LRS and DLE Same as embodiment See Data Embodiments: LRS Search Users can view the LRS and
Users 6.3.3.7 Modify LRS Embodiment Description	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners  Provide user with the ability to modify a proposed LRS Only creators/designers can modify LRS. In addition, FMT can store an audit trail of modifications to each LRS. See Data Embodiments: LRS & Hand-Off Package Users retrieve specific	35 E	RS details ource for all the data eleme AS 6.3.3.9 View LRS a Embodiment Description Data	ents which are required for this embodiment:  nd DLE Plans  Provide users the ability to view a LRS and DLE Same as embodiment See Data Embodiments: LRS Search Users can view the LRS and DLE associated with it from within FMT for a particular
Users  5.3.3.7 Modify LRS  Embodiment  Description	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners  Provide user with the ability to modify a proposed LRS Only creators/designers can modify LRS. In addition, FMT can store an audit trail of modifications to each LRS. See Data Embodiments: LRS & Hand-Off Package	35 S E — 40 —	RS details ource for all the data eleme AS 6.3.3.9 View LRS a Embodiment Description Data	ents which are required for this embodiment:  nd DLE Plans  Provide users the ability to view a LRS and DLE Same as embodiment See Data Embodiments: LRS Search Users can view the LRS and DLE associated with it from within FMT for a particular LRS or searching for one. The user can view a LRS according
Users  5.3.3.7 Modify LRS  Embodiment  Description	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners  Provide user with the ability to modify a proposed LRS Only creators/designers can modify LRS. In addition, FMT can store an audit trail of modifications to each LRS. See Data Embodiments: LRS & Hand-Off Package Users retrieve specific LRS through the on-screen interface, and edit or	35 E	RS details ource for all the data eleme AS 6.3.3.9 View LRS a Embodiment Description Data	ents which are required for this embodiment:  nd DLE Plans  Provide users the ability to view a LRS and DLE Same as embodiment See Data Embodiments: LRS Search Users can view the LRS and DLE associated with it from within FMT for a particular LRS or searching for one. The
Users  5.3.3.7 Modify LRS  Embodiment  Description  Data  System Behavior	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners  Provide user with the ability to modify a proposed LRS Only creators/designers can modify LRS. In addition, FMT can store an audit trail of modifications to each LRS. See Data Embodiments: LRS & Hand-Off Package Users retrieve specific LRS through the on-screen interface, and edit or delete them. Loop Capacity Mangers, Long Term Planners, IOF Planners Once published, track changes	35 S E — 40 —	AS  6.3.3.9 View LRS a  Embodiment  Description Data  System Behavior	ents which are required for this embodiment:  nd DLE Plans  Provide users the ability to view a LRS and DLE Same as embodiment See Data Embodiments: LRS Search Users can view the LRS and DLE associated with it from within FMT for a particular LRS or searching for one. The user can view a LRS according to their user permissions. Loop Capacity Mangers, Long
Users  6.3.3.7 Modify LRS  Embodiment  Description  Data  System Behavior  Users	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners  Provide user with the ability to modify a proposed LRS Only creators/designers can modify LRS. In addition, FMT can store an audit trail of modifications to each LRS. See Data Embodiments: LRS & Hand-Off Package Users retrieve specific LRS through the on-screen interface, and edit or delete them. Loop Capacity Mangers, Long Term Planners, IOF Planners	35 S E — 40 —	RS details ource for all the data eleme AS  6.3.3.9 View LRS a  Embodiment Description Data System Behavior  Users	ents which are required for this embodiment:  nd DLE Plans  Provide users the ability to view a LRS and DLE Same as embodiment See Data Embodiments: LRS Search Users can view the LRS and DLE associated with it from within FMT for a particular LRS or searching for one. The user can view a LRS according to their user permissions. Loop Capacity Mangers, Long
Users  6.3.3.7 Modify LRS  Embodiment  Description  Data  System Behavior  Users	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners  Provide user with the ability to modify a proposed LRS Only creators/designers can modify LRS. In addition, FMT can store an audit trail of modifications to each LRS. See Data Embodiments: LRS & Hand-Off Package Users retrieve specific LRS through the on-screen interface, and edit or delete them. Loop Capacity Mangers, Long Term Planners, IOF Planners Once published, track changes made to LRS by any/all users. Track all state changes. Any LRS (primary or alternatives) can be modified until an	40 45 50	RS details ource for all the data eleme AS  6.3.3.9 View LRS a  Embodiment Description Data System Behavior  Users	Provide users the ability to view a LRS and DLE Same as embodiment See Data Embodiments: LRS Search Users can view the LRS and DLE associated with it from within FMT for a particular LRS or searching for one. The user can view a LRS according to their user permissions. Loop Capacity Mangers, Long Term Planners, IOF Planners.  iple LRS for Same Geographic Arc
Users  5.3.3.7 Modify LRS  Embodiment  Description  Data  System Behavior  Users	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners  Provide user with the ability to modify a proposed LRS Only creators/designers can modify LRS. In addition, FMT can store an audit trail of modifications to each LRS. See Data Embodiments: LRS & Hand-Off Package Users retrieve specific LRS through the on-screen interface, and edit or delete them. Loop Capacity Mangers, Long Term Planners, IOF Planners Once published, track changes made to LRS by any/all users. Track all state changes. Any LRS (primary or alternatives) can be modified until an LRS reaches the 'build' state. When the primary LRS	40 45 50	AS  6.3.3.9 View LRS a  Embodiment Description Data System Behavior  Users  6.3.3.10 View Mult	ents which are required for this embodiment:  Ind DLE Plans  Provide users the ability to view a LRS and DLE Same as embodiment See Data Embodiments: LRS Search Users can view the LRS and DLE associated with it from within FMT for a particular LRS or searching for one. The user can view a LRS according to their user permissions. Loop Capacity Mangers, Long Term Planners, IOF Planners.  Iple LRS for Same Geographic Are  Provide users with the ability to view multiple Location Relief Strategies for same
Users  5.3.3.7 Modify LRS  Embodiment  Description  Data  System Behavior  Users	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners  Provide user with the ability to modify a proposed LRS Only creators/designers can modify LRS. In addition, FMT can store an audit trail of modifications to each LRS. See Data Embodiments: LRS & Hand-Off Package Users retrieve specific LRS through the on-screen interface, and edit or delete them. Loop Capacity Mangers, Long Term Planners, IOF Planners Once published, track changes made to LRS by any/all users. Track all state changes. Any LRS (primary or alternatives) can be modified until an LRS reaches the 'build' state, alternatives are 'frozen'	40 45 50	RS details ource for all the data eleme AS  6.3.3.9 View LRS a  Embodiment Description Data System Behavior  Users  6.3.3.10 View Mult  Embodiment  Description	Provide users the ability to view a LRS and DLE Same as embodiment See Data Embodiments: LRS Search Users can view the LRS and DLE associated with it from within FMT for a particular LRS or searching for one. The user can view a LRS according to their user permissions. Loop Capacity Mangers, Long Term Planners, IOF Planners.  Provide users with the ability to view multiple Location Relief Strategies for same geographic area. Same as embodiment
Users  5.3.3.7 Modify LRS  Embodiment  Description  Data  System Behavior  Users	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners  Provide user with the ability to modify a proposed LRS Only creators/designers can modify LRS. In addition, FMT can store an audit trail of modifications to each LRS. See Data Embodiments: LRS & Hand-Off Package Users retrieve specific LRS through the on-screen interface, and edit or delete them. Loop Capacity Mangers, Long Term Planners, IOF Planners Once published, track changes made to LRS by any/all users. Track all state changes. Any LRS (primary or alternatives) can be modified until an LRS reaches the 'build' state. When the primary LRS reaches the 'build' state, alternatives are 'frozen' and cannot be modified. At this point, alternatives could	40 45 50 55 —	RS details ource for all the data eleme AS  6.3.3.9 View LRS a  Embodiment Description Data System Behavior  Users  6.3.3.10 View Mult  Embodiment  Description Data	ents which are required for this embodiment:  Ind DLE Plans  Provide users the ability to view a LRS and DLE Same as embodiment See Data Embodiments: LRS Search Users can view the LRS and DLE associated with it from within FMT for a particular LRS or searching for one. The user can view a LRS according to their user permissions. Loop Capacity Mangers, Long Term Planners, IOF Planners.  Iple LRS for Same Geographic Are  Provide users with the ability to view multiple Location Relief Strategies for same geographic area. Same as embodiment See Data Embodiments: LRS & Hand-Off Package
Users  5.3.3.7 Modify LRS  Embodiment  Description  Data  System Behavior  Users	LRS and copy it to a new page. Loop Capacity Mangers, Long Term Planners, IOF Planners  Provide user with the ability to modify a proposed LRS Only creators/designers can modify LRS. In addition, FMT can store an audit trail of modifications to each LRS. See Data Embodiments: LRS & Hand-Off Package Users retrieve specific LRS through the on-screen interface, and edit or delete them. Loop Capacity Mangers, Long Term Planners, IOF Planners Once published, track changes made to LRS by any/all users. Track all state changes. Any LRS (primary or alternatives) can be modified until an LRS reaches the 'build' state. When the primary LRS reaches the 'build' state, alternatives are 'frozen' and cannot be modified. At this	40 45 50 55 —	RS details ource for all the data eleme AS  6.3.3.9 View LRS a  Embodiment Description Data System Behavior  Users  6.3.3.10 View Mult  Embodiment  Description	Provide users the ability to view a LRS and DLE Same as embodiments: LRS Search Users can view the LRS and DLE associated with it from within FMT for a particular LRS or searching to their user permissions. Loop Capacity Mangers, Long Term Planners, IOF Planners.  Provide users with the ability to view multiple Location Relief Strategies for same geographic area. Same as embodiment See Data Embodiments: LRS &

66

	-continued			-continued
Users	or more LRS on-screen at any given time. The user can toggle this feature on and off. Loop Capacity Mangers, Long Term Planners, IOF Planners.	5	Users	Loop Capacity Mangers, Long Term Planners, IOF Planners
6.3.3.11 Capture Lifeature by User	RS Notes Associated with a Graphical	10	6.3.3.15 Provide Vie	w Printing
			Embodiment	Print all views available
Embodiment	Capture LRS, and information about the LRS notes including the date created and	1.5	Description	on-screen. The FMT client can support all Windows-standard functionality including
Description Data System Behavior	the user that entered the comment. Same as embodiment None The system should provide a freeform field that captures	15		save, print, cut, paste, copy, portrait, landscape, paper size, etc. In addition, the client can provide the user with the ability to assign a title to the printed document.
	LRS notes. The system should assign the current day's date in a separate field.	20	Data System Behavior	None System can print all views, including graphical (geographical and facilities)
Users	Loop Capacity Mangers, Long Term Planners, IOF Planners.	25	Users	and tabular data of an LRS.  Loop Capacity Mangers, Long Term Planners, IOF Planners
6.3.3.12 Manage G	raphical Feature LRS Notes by User		Spatial Embodiment	Allow user to print graphical representations of LRS
E I I' .	D 11 914		Scope for FAS:	
Embodiment	Provide user with the ability to manage LRS notes through a graphical feature by user.	30	Print LRS tabular data Scenario:	
Description Data	Same as embodiment Same data as for a tabular note, but associated with planned		User selects Print. LRS of Data elements that should	details are printed d be displayed on the FAS screen:
System Behavior	feature rather than tabular LRS. Users with the access to FMT	35	LRS details	
Users	can enter LRS notes through a graphical feature. The system can output the request by user. All FMT users	40	6.3.3.16 Create an E and Location	Equipment Plan Associated to a LF
6.3.3.13 Link to Ta	bular LRS Data at Location Features		Embodiment	Create an equipment plan associated to a LRS and location.
Embodiment	Provide an internal link to tabular LRS data at location features	45	Description Data System Behavior	Same as embodiment None System should have the ability for the user to create an
Description Data System Behavior Users	Same as embodiment None User interface can interact with a link to the tabular planning data. Loop Capacity Mangers, Long	50	Users	equipment LRS that is associated with its location and LRS ID. Loop Capacity Mangers, Long Term Planners, IOF Planners
6.3.3.14 Measure S	Term Planners, IOF Planners	55	6.3.3.17 Create Fibe. Sheath	r Strand Plans Associated to LRS a
Embodiment	Measure both horizontal and loop distances for a		Embodiment	Create Fiber Strand Plans associated to a LRS and
Description	Location Relief Strategy (LRS) System measures strand distance in feet or meters.	60	Description Data System Behavior	Sheath. Same as embodiment None System should allow users to
Data System Behavior	None User interface can assign appropriate distance based on scale of current on-screen view.	65	Users	create fiber strand plans that are associated with Location Relief Strategy and sheath. Loop Capacity Mangers, Long Term Planners, IOF Planners

#### -continued

Spatial Embodiment	User can modify complement data of existing facilities as a part of a LRS.
Scope for FAS:	

FAS captures Fiber interest, but user must manually enter fiber strands in LRS tabular; there is not check between Spatial and FAS for a fiber interest Scenario:

User opens a LRS. User modifies complements on existing fiber sheaths so that desired fiber strands are energized in the desired manner. User then opens the LRS detail screen and enters the desired fiber strands in the Fiber Strand field. An interest is then created.

Data elements that should be displayed on the FAS screen:

Logical strand
Source for all the data elements which are required for this embodiment:

user

#### 6.3.3.18 Provide Summary Reports

FMT can have the ability to generate summary reports on a company's fiber optic assets. In summary, and at minimum, FMT can produce the following information:

Report	Description
Central Offices by District	The report includes summary information of Central Offices (Wire Centers) by District.
Equipment by Central Office	This report includes all fiber-related equipment, and summary information of that equipment, associated with a particular Central Office.
Equipment by Remote Terminal	This report includes all fiber-related equipment, and summary information of that equipment, associated with a particular Remote Terminal.
Equipment, Plant Assets by Fiber Strand	This report includes all fiber-related equipment, and summary information of that equipment (including location) associated with a particular Fiber Strand.

#### 6.3.3.19 Create Ad Hoc Monitoring Queries and Reports

Embodiment	Create Ad Hoc monitoring queries and reports for	
	specialized and unpredict-	50
	able monitoring tasks.	
Description	Reports may be design and	
	saved from a separate	
	application, but report	
	record selection, previewing, and	
	writing must be integrated	55
	into FMTs planning layer.	
Spatial Embodiment	Provide spatial query	
	capabilities in a user-friendly	
	manner which also prevents	
	users from creating	
	dangerous, unworkable, or	
	"expensive" queries	60
Scope for FAS:		

Create a means of 1) creating custom reports and 2) saving the requests so that the reports can be reproduced. This tool should be capable of querying data related to equipment Xbox, CSA. Fiber, and LRS and performing joins. The user should be able to specify field, operator (e, >, <, Like), value

#### -continued

(including wildcard), and and/or relationship. This embodiment may not include the ability to perform mathematical operations (sum, percent, etc.) but the user may be able to save the result set so that it may be opened in another application for that purpose. Data elements that should be displayed on the FAS screen:

As requested by user Source for all the data elements which are required for this embodiment:

10 FAS datawarehouse

#### 6.3.3.20 LRS Handoff Package

Embodiment	LRS handoff data that
	describes the Location Relief
	Strategy must be accessible
	by other users and the PM
	Tool.
Description	The document must meet
	the minimum handoff
	embodiment as described.
Data	See Data Embodiment: LRS &
	Hand-Off Package
Scope for FAS:	

25 Upon user selecting "handoff" pass appropriate data to PM Tool in a realtime manner. Scenario:

User selects LRS. User ensures that LRS is 1) primary and 2) published. User then selects "handoff." A PM Tool document is automatically

30 generated. Alternatively:

User selects a private, alternative LRS. User attempts to generate handoff package. System notifies user that the LRS must first be published and primary, would the user like to do this now; if so then primary LRS "x" must become alternative, proceed?

35 User selects proceed, and a PM Tool document is automatically generated.

Data elements that should be displayed on the FAS screen:

See PM Tool interface

Source for all the data elements which are required for this embodiment:

FAS

#### 6.3.3.21 Monitor Facility and Fills

Embodiment	Monitor facility and fills
	by generating actual and
	forecasted network usage.
Description	FACILITY PLANNERSs need to
	generate, view, print
	reports of actual and fore-
	casted network usage. Reports
	should be available at
	various levels of the network
	segments.
	Monthly details: these
	reports list usage
	statistics by month for
	a 12-month period.
	History and Forecast:
	these reports list usage
	statistics by year, as well as disconnects, and
	defects in the past
	By service category and
	architecture: these
	reports list network
	usage organized by type of
	service and system
	architecture

40

69

#### 6.3.3.22 Provide Inventory Tasks on Equipment/Site Details

Embodiment	Provide information for
	inventory tasks on existing and
	proposed equipment and
	site details.
Description	FMT must provide access to
*	individual network elements
	starting from a district at
	the top of the inventory hierarchy.
Scope for FAS:	

Existing iView functionality for all equipment, not just that which is found in LEIM.

Source for all the data elements which are required for this embodiment:

Same as iView functionality today.

#### 6.3.3.23 Maintain Editing History

Embodiment	Maintain editing history	
	of each Location Relief	
	Strategy (LRS)	
Description	The history can consist of	
•	a list of modifiers and the date of	
	their last change.	
Scope for FAS:	-	

Maintain list of users and timestamps of edits

User selects LRS and makes modifications. User's ID and timestamp are recorded and displayed upon request.

Data elements that should be displayed on the FAS screen:

User name, ID, timestamp

Source for all the data elements which are required for this embodiment:

FAS

#### 6.3.3.24 Create "Publish" Pop-Up Window

Embodiment	Create a pop-up window every time a user exists his/her	
	planning screen	
Description	Once the user has finished	
	a session of creating a LRS and	45
	wants to exit and log out -	
	the system can pop up a screen	
	and ask the user: Do you	
	want to Publish? The user can	
	click on Yes or No-Remind	
	me in days. (The number	50
	of days can be determined	50
	in the design stage)	
Scope for FAS:	,	

Create Publish "nag screen" Scenario:

User selects LRS and makes edits. Upon clicking the Save button the user sees a screen which encourages him to publish the LRS. Data elements that should be displayed on the FAS screen:

Publish "nag screen"

Source for all the data elements which are required for this embodiment:

Publish popup screen with yes/no buttons

#### 6.4 Exit, Session, Recovery, and Cleanup

The FMT client can exit gracefully. Upon exit, the client can perform all necessary cleanup for any locally stored,

70

temporary files. If a user's session is interrupted (due to a power outage for example), the client can have the ability to recover the session.

6.5 Performance

FMT should be pleasant for user to user; the application should respond to users' selections quickly. Action should be taken to ensure that user wait time is minimized. This goes for both the graphical and tabular tools. For example:

- 1) Interactive task response times—2 seconds or less.
- 2) Creation of print file in less than 2 seconds (file size 1 MB).
- 3) Design session startup
  - a) From File (4 MB of graphics)—15 seconds or less
  - b) From database—1 minutes or less
- 4) User interface is event driven (users must understand mouse movements).
- 5) Screen refreshes—3 seconds or less.
- 6) Standard data queries—3 seconds or less.
- 7) Minimum mouse travel.
- 8) Optimum Use of Keyboard and mouse interactions (minimized user movements required).
- 9) Response time on customer tools as good as standard tools.
- 7 External System

Purpose: This section describes embodiments for the interfaces between OPEDS and the various external systems that can provide data for FMT. Data transmission in the network can comprise proprietary and open standards and methodologies.

Discussion: Data transmission in the network can involve the use of external system interfaces (or "contracts") that are implemented using one of the following accepted communication standards listed below (see Table 3)

TABLE 3

St	Standard Communication Methods				
BUFIT	A file-based transmission method, BUFIT is most often used to send multiple records of data in a single file from one system to another. BUFIT transactions are normally associated with batch processes (i.e. each night a system sends all of the current day's order records to the archive system).				
Navigator <sup>1</sup>	A structure-based transmission method, Navigator is used to send memory structures from one system to another. Navigator transactions are normally associated with interactive processes and can sometimes involve query and response scenarios (i.e. System A sends a request to System B for data, System B interactively sends data back to System A).				
Orbix	Orbix provides an Object Request Broker (ORB) that behaves like Navigator in that it is most often used for immediate transactions between interactive processes.				

Each contract can have an associated version number (e.g., 60 the first, "0001," the second "0002" and so on). A process can assign the next version number if the contents of the contract change, such as the addition of a new field or possibly a change in the expected contents of an existing field. All programs initiating contracts can tag them with appropriate version numbers. Furthermore, all receiving programs should recognize the version of the contract upon receiving them, and act on that version appropriately. For example, if a con-

71

tract is on its third version, the program that receives the contract should accept versions 1, 2 or 3 of the contract and process it accordingly.

The OPEDS Process/Data management layer can manage the process of sending all outgoing contracts from an OPEDS 5 point of view as well as receiving all incoming contracts from an OPEDS point of view. This can include storing and retrieving the data for other processes requesting the data.

Specific information for each of FMT's external system  $_{10}$ interfaces is outlined below.

Note: FMT may acknowledge positive receipt of the data.

#### 7.1 External Systems Communications

#### 7.1.1 LECIII

System Overview	Loop Electronics Coordination	
·	Version 3 (LEC III) is a	
	mainframe based budgeting,	
	scheduling, forecasting, and	
	tracking toll for DLC equip-	
	ment. It stores equipment, cost,	
	and scheduling information	
	along with user plans for DLC	
	work with which provides in-	
	formation through a series of	
	reports and an ad hoc query system.	
Embodiment	The FMT system can establish	
	a "process" type of interface	
	with LEC III in which users	
	can receive data in FMT based	
	upon the entry of LECIII ID.	
Process	The LEC III ID entered into	
	FMT, a process can then be	
	triggered that can retrieve the	
	data associated with the ID.	
Response	FMT must acknowledge positive	
	receipt of the data. Data is	
	then displayed in FMT.	

#### 7.1.1.1 LEC III Data Embodiments

Fields	Description	Data Type	Max. Char.	
LEC III ID	Numbering scheme brought over by LEC			_
Equipment Type	Product description of DLE equipment			
Quantity	Total number of a specified equipment type			
#System	System number of system to be turned up			
Mode	Mode "I" "II" or "III"			
TR303 Line	DLC type			
#DS1 Req.	Required number of DS1s			
DLC System Type	Manufacturer code			
TR303/Tr008	Terminal type			
RDSC	Code to be used to order			
	equipment associated			
	with this LRS (may be			
	manually entered or fed			
	from LECIII)			

#### 7.1.2 LOC/CLLI

System Overview

This system is used to request Area Numbers and CLLI Code Information. Users can retrieve existing CLLI codes or submit requests to CLLIADM via Open Mail to create new codes,

72

#### -continued

	modify and delete existing
	codes. This system is integrated
	with LEC III.
Embodiment	The LOC/CLLI system can trans-
	mit the specified data
	elements to FMT within the
	agreed upon time frame nightly,
	including weekends. The data
	from LOC/CLLI should be a
	"delta" from the last data
	set that was indicated as successfully
	received from FMT. FMT can
	load the data from LOC/CLLI
	within a timeframe that is
	acceptable based on the amount of
	data received from LOC/CLLI
	and the necessary business
	rules.
Response	FMT must acknowledge positive
	receipt of the data.
	receipt of the data.

System Overview	LFACS (Loop Facilities Assignment
	and Control System) -
	LFACS is an inventory and
	assignment system for the outside
	plant (local loop) facilities
	which support DS0-level (and, in
	some cases, DS-1-level) services.
	LFACS maintains an
	inventory of customer locations
	and the outside plant facilities,
	which serve each location.
Embodiment	Execute inquiries and reports
	against the LFACS database
	from within a FMT session.

#### 7.1.4 FOX/DSX/TEOPS

System Overview	FOX (Fiber Optic Connect System)
	Module of TEOPS (Telephone
	equipment processing system)
	where DSX or LGX assignments
	are made when new
	equipment is added to a
	central office.
Embodiment	FOX can transmit the specified
	data elements to OPEDS
	within an agreed upon time
	frame nightly, including weekends.
	The data from FOX should be a
	"delta" from the last data set
	that was indicated as successfully
	received from OPEDS. The
	OPEDS system can load the data
	from FOX and the necessary
	business rules.
Response	OPEDS may acknowledge positive
•	receipt of the data.

#### 7.1.4.1 FOX/DSX Data Embodiments

	Fields	Description	Data Type	Max. Char.
65	Bay Panel Jacks LTR	Identifier for the bay and panel		

## **74**

## -continued

elds	Description		Max. Char.			examine this issue further. The existing LEIM extract for FAS can be modified		
ssigned equipment ssigned location nit/shelf ircuit EO	Type of assigned equipment to a bay Location of the equipment The shelf number Type of circuit Associated unique identifier	o a bay 5		5	Embodiment Description	FAS can be modified Allow user to send "update" data for 1 location It is feasible to have a request and response between FMT and LEIM to get a Location		
ote	used to place equipment Remarks field			10		update. It could be batch, possibly overnight, using FTP if variances are approved		
7.1.5 TIRKS				15	7.1.7 BCM			
System Overvie				13				
Embodiment	and central office informatio TIRKS can provide current of within 24 hours. There may be two possible ways to accomplish this: 1) receive be sets from TIRKS on a nightle basis, or 2) establish a "quer and response" type of interface with TIRKS in whit users can request current dat	data bulk data y y ich FMT		20	System Overview	The Telecommunications Company Construction Management system is a web-based application designed to assist in planning, forecasting, tracking, and controlling capital retirement and maintenance budgets for Central Office Equipment (COE), Outside Plant (OSP), Land and Building (L&B), and Plug-in Authorizations.		
	The first option may be preferable so long as the dat is such that TIRKS can prov OPEDS with "deltas" and th amount of data is such that t OPEDS database can store it	a ide e he		25	7.1.8 PM TOOL			
Response	redundantly. OPEDS must acknowledge preceipt of the data.	oositive		30	System Overview	PM TOOL (Project Management Tool), serves as a shared database between BST and the		
7.1.6 LEIM				35	Embodiment	Supplier in which all identified engineering embodiments can be logged and then tracked from identification through completion. FMT can establish a "process" type of interface with PM		
System Overvie	Module) Corporate repositor of OSP Digital Loop Electron	ry				TOOL in which users can receive data in FAS based upon the entry of certain data elements. The FAS tables can contain PM		
Embodiment	Data.  LEIM can provide current d: within 24 hours. There may two possible ways to accomp this: 1) receive bulk data sets from LEIM on a nightly bas	be plish s		40		Tool data elements i.e. PM Tool ID, date(s) etc. When the ID or other predetermined data element is entered into FMT, a contract can be triggered that		
	or 2) establish a "query and response" type of interface with LEIM in which FMT u- can request current data. The			45	Process	can retrieve the associated data and display the appropriate information in FAS. User generates a hand-off		
	first option may be preferable long as the data is such that	le so			Response	package All LRS data is sent to PM Tool.		

Fields	Description	Data Type	Max. Char.
PM Tool Id	PM Tool item# (unique in component)		
LRS Id	FAS LRS ID (unique in FAS database)		
Wire Center	Wire center CLLI for this plan		
Location	Location of plan		
Job Title	User defined short description of work to be performed		
EWO	Auth number fed from PM Tool to FAS Plan		

Fields	Description	Data Type	Max. Char.
Local Category	Used in PM Tool to categorize work		
Metrics Category	Used in PM Tool to categorize work		
Taper Codes	Numerical representation of an interface to be		
	monitored		
Associated PM Tool	Used in PM Tool to associate other PM Tool items		
Scope	Free form description of work to be performed		
Status	Free form description of status of LRS or handoff		
	document to be performed		
FACILITY	Owner of FAS plan		
PLANNERS	For form intensting and the last		
Copper Sizing Criteria	Free form instructions concerning how copper cables		
Cable Count	should be sized on this plan  Copper cable name and pair range to be used in this		
Cable Couli	plan		
Fiber Sizing Criteria	Free form instructions concerning how fiber cables		
riber bizing Criteria	should be sized on this plan		
Cable Count	Fiber cable name and pair range to be used in this plan		
Mandatory Splice	Free form comments indicating required splice points		
Location	in a LRS involving fiber		
Service Required	Date by when FACILITY PLANNERS believes		
1	service is required for this plan		
Approval Date	Date when the auth number associated with the PM		
	Tool document is approved in JMS		
Hand-Off Date	Date when hand off package is generated (FAS LRS is		
	entered into PM Tool)		
Construction Close	Date when auth number associated with the PM Tool		
Date	document is closed in OSPCM		
Cancellation Date	Date when auth number associated with the PM Tool		
	document is cancelled in JMS		
Permit Type	Type of permit required		
Grantor	Grantor of permit		
Date Permit Received	Date notification of approval of permit received		
Date Permit	Data approval of parmit requested		
Requested	Date approval of permit requested		
Easement Required	Yes/no indicator of whether an easement can need to		
Lasement Required	be obtained as a part of this plan		
Date Easement	Date easement requested		
Requested	1		
Date Easement	Date easement received		
Received			
Co Mux Location	Relay rack location of Central office Mux		
Fiber Assignment	Fiber assignment for connecting equipment		
Co LGX Position	Central office bay location of the central office LGX		
TEO	Associated TEO which places equipment for this plan		
RDSC Code	Code to be used to order equipment associated with		
	this LRS (may be manually entered or fed from		
	LECIII)		
Clli	LOC_CLLI of remote terminal		
Area Number	Tax code associated with RT LOC_CLLI		
Address	Address of remote terminal where work is to be		
Sita#	performed  CSA or location ID of remote terminal where I BS is to		
Site#	CSA or location ID of remote terminal where LRS is to take place		
RT Type	Structure type		
Channel Banks	Number of channel banks to be added on this plan		
Added	Number of chainer banks to be added on this plan		
Commons Added			
DLC	Indicates whether system is to be turned up as		
	integrated or universal. PM Tool currently only		
	supports these options, a modification should be made		
	to also accept TR303). This field may be modified		
	further to indicate the turning up of a Mux		
COT	Position of central office connection (COT location or		
	switch peripheral bay/panel/jack location)		
DS1 Assignment	FACS cable pair(s) which can feed the system being		
	turned up		
System Type	System type (s1c5, discs, etc.)		
Mode	Indicator of number of DS1's being used to turn up the		
~	system		
System#	System number of system to be turned up		
Count	Cable name and pair range to originate from this piece		
	of equipment		
Fitl Out Count	Cable name and pair range to originate from this piece		

#### 7.1.9 TEOPS -continued

System Overview  Embodiment	TEOPS is the tool which is used for creating and monitoring Telephone Engineering Orders. FMT may transmit data to and	5	Process Response	TBA All LRS data is sent to PM Tool. Once the data is received PM Tool returns a PM Id.
Emodament	retrieve data from TEOPS on an as needed basis. These transactions can be real time.		8 Data Embodiments	_

## 8 Data Embodiments 8.1 LRS & Hand-Off Package

**78** 

Data Item	Description	Data Type	Max. Char.	Source (Primary, Secondary)
		Туре	Chai.	Secondary)
LRS Id	FAS LRS ID number (unique in FAS database)			
PM Tool Id	PM Tool item# (unique in			
_	component)			
Comment	Free form field for comments which should be stored but not			
	included in the handoff			
n	package			
Equipment ID	LEIM unique wire center Identifier			
Entity	PM Tool entity (derived from			
	ST/NVP)			
Component	PM Tool component (derived from WC district)			
Mux Ports	Muldem/Slot/Port assigned to			
	a system being turned up.			
Status	Indicator of whether LRS is			
	public or private and if a handoff package has been			
	generated			
Wire Center	Wire center CLLI for this LRS			
Location  Job Title	Location of LRS address User defined short description			
	of work to be performed			
EWO	Auth number fed from PM			
Local Category	Tool to FAS LRS Used in PM Tool to categorize			
Docur Category	work			
Metrics Category	Used in PM Tool to categorize			
Taper Codes	work Numerical representation of an			
Taper Codes	interface to be monitored			
Associated PM Tools	Used in PM Tool to associate			
Associated LRS	other PM Tool items Associates current LRS with			
2 Bootelated Erto	other FAS LRS			
Associated Facility Route	Associates current LRS with			
Scope	FMT proposed facility routes Free form description of work			
Беоре	to be performed			
Status	Free form description of status			
	of LRS or handoff document to			
FACILITY PLANNERS	be performed Owner of FAS LRS			
Copper Sizing Criteria	Free form instructions			
	concerning how copper cables			
	should be sized on this LRS			
Cable Count	Copper cable name and pair range to be used in this LRS			
Fiber Sizing Criteria	Free form instructions			
	concerning how fiber cables			
	should be sized on this LRS			
Cable Count	Fiber cable name and pair			
Mandatory Splice Location	range to be used in this LRS Free form comments indicating			
	required splice points in a LRS			
	involving fiber			
Service Required	Date by when FACILITY			
	PLANNERS believes service is required for this LRS			
Approval Date	Date when the auth number			
	associated with the PM Tool			
	document is approved in JMS			

	continued			
Data Item	Description	Data Type	Max. Char.	Source (Primary, Secondary)
Hand-Off Date	Date when hand off package is generated (FAS LRS is entered into PM Tool)			
Construction Close Date	Date when auth number			
	associated with the PM Tool			
Cancellation Date	document is closed in OSPCM Date when auth number			
	associated with the PM Tool			
Down it True	document is cancelled in JMS			
Permit Type Grantor	Type of permit required Grantor of permit			
Date Permit Received	Date notification of approval			
Date Permit Requested	of permit received  Date approval of permit			
Date I cliffit Requested	requested			
Easement Required	Yes/no indicator of whether an			
	easement can need to be obtained as a part of this LRS			
Date EasementRequested	Date easement requested			
Date EasementReceived	Date easement received			
Co Mux Location	Relay rack location of Central office Mux			
Fiber Assignment	Fiber assignment for			
Co LGX Position	connecting equipment Central office bay location of			
CO LGA FOSITION	the central office LGX			
TEO	Associated TEO which places			
RDSC Code	equipment for this LRS Code to be used to order			
RDSC code	equipment associated with this			
	LRS (may be manually entered			
Clli	or fed from LECIII)  LOC_CLLI of remote terminal			
Area Number	Tax code associated with RT			
A didunan	LOC_CLLI			
Address	Address of remote terminal where work is to be performed			
Site#	CSA or location ID of remote			
	terminal where LRS is to take place			
RT Type	Structure type			
Channel Banks Added	Number of channel banks to be			
Commons Added	added on this LRS			
DLC	Indicates whether system is to			
	be turned up as integrated or			
	universal. PM Tool currently only supports these options, a			
	modification should be made			
	to also accept TR303) This field may be modified further			
	to indicate the turning up of a			
	Mux			
Cot	Position of central office connection (COT location or			
	switch peripheral			
Ds1 Assignment	bay/panel/jack location) FACS cable pair(s) which can			
Ds1 Assignment	feed the system being turned			
	up			
System Type Mode	System type (s1c5, discs, etc.) Indicator of number of DS1's			
Wode	being used to turn up the			
St#	system			
System#	System number of system to be turned up			
Co DSX RT-Unit/Jacks	Jack assignments of DSX for			
Muy Poto	COT			
Mux Rate	Indicates rate of optics and capacity of Multiplexer shelf			
	(e.g. OC3+, OC1, OC192)			

Data Item	Description	Data Type	Max. Char.	Source (Primary, Secondary)
Tid	Target identifier for SONET			
SCID Architecture	devices Sonet Carrier Identifier Indicator of architecture of fibers feeding device (e.g. diverse, collapsed)			
Count	Cable name and pair range to originate from this piece of equipment			
Fitl Out Count	Cable name and pair range to originate from this piece of FITL equipment			
LOC ID	LEIM location ID is a unique identifier with a W/C to identify a structure.			
Timeslot	Timeslot information for assignment of DS3 data in TIRKS			

## 8.2 LRS Search

Data Definition	Description	Data Type	Max Char.	Source (Primary, Secondary)
Wire Center	Clli code for Wire Centers			
Clli				
Taper Code	The taper code associated			
	with the terminal			
Terminal	Address of the terminal			
Address				
LRS ID	Unique LRS identifier			
	assigned by FAS			
PM ID	Numbering scheme brought			
	over by PM Tool			
BCM TEO/Proi	Numbering scheme brought			
DCM TLO/TTOJ	over by BCM.			
LEG III ID				
LEG III ID	Numbering scheme brought			
	over by BCM.			

40

## 8.3 Facility Route Search

Data Definition Description	Data Type	Max. Char.	Source (Primary, Secondary)	45
-----------------------------	--------------	---------------	--------------------------------	----

## 8.4 Equipment Attributes

Data Definition	Description	Data Type	Max Char.	Source (Primary, Secondary)
CLLI# (Common Language Location Identifier)	Common Language Location Identifier	Text	8	LEIM, TIRKS, LOC/CLLI and FAS
CLEI # (Common Language Equipment Identifier)	Code that uniquely identifies an item of DLE equipment	Text	12	LEIM, TIRKS
Address	Street Address	Text	20	LEIM, LOC/CLLI, FAS
Location	Location inside a CO or RT where a specific item of equipment resides	Text	12	LEIM, FAS
Equipment Type	Product description of DLE equipment	Text	30	LEIM, TIRKS, LFACS

Data Definition	Description	Data Type	Max Char.	Source (Primary, Secondary)
RDSC (Regional	Code that provides a DLE	Text	20	LEIM
Design Source Code)	equipment manufacturer's standard product configuration and prices			
Customer Name	Name of customer served by an item of DLE equipment	Text	25	LEIM or personal notes
AWF (Alarm Wiring Configuration)	Standard configuration that corresponds to the DLE powering configuration	Numeric	4	LEIM
TEO # (Telephone Equipment Order)	Number assigned to a purchase order of DLE equipment	Text	18	LEIM, FOX
EWO # (Engineering Work Order)	Engineering work order that placed or modified that piece of equipment	Text	10	FAS, LEIM
Feeder Route #	Used for provisioning	Text	2	LEIM
Carrier#	Used for provisioning	Text	6	LEIM
Allocation #	Used for provisioning	Text	6	LEIM
Distribution #	Used for provisioning	Text	6	LEIM
Status	Assignment condition - working, assigned, spare, planned	Text	10	LEIM, TIRKS, Personal Notes

## 8.5 MUX

Data Definition	Description	Data Type	Max Char.	Source (Primary, Secondary)
DSX Assignment	DS1 or DS3 Termination	Text	6	TIRKS, LEIM, FOX
System #	Administration # assigned to MUXs	Nume ric	4	TIRKS, LEIM, LFACS
Software Generic	Software version supporting an item of DLE equipment	Text	10	TIRKS, LEIM
TID # (Target ID)	Combination of CLLI, System Type and System Number	Text	20	TIRKS, LEIM
Wavelength	Wavelength in nanometers that equipment is operating	Text	10	TIRKS, LEIM
Bandwidth	Maximum MBs per second of data that an item of equipment can transmit	Text	8	TIRKS, LEIM
Bandwidth Capacity	Maximum Bandwidth	Text	8	TIRKS, LEIM
FOT Assignment	LGX termination point	Text	10	LEIM (loop); FOX, TIRKS (IOF)
MD Counts	MUX Distribution Counts	Text	16	LFACS, LEIM
Configuration	Sonet or Assync, and the ring configuration	Text	20	TIRKS, LEIM
SCID # (Sonet Circuit ID)	Identification number given to Sonet Mux systems.	Text	8	LEIM, TIRKS
DS3 Circuit ID	Unique DS3 or STS-1 circuit	Text	20	TIRKS
DS1 Circuit ID	Unique DS1 circuit ID	Text	20	LFACS, TIRKS
OCN Circuit ID	Unique OCN circuit ID	Text	20	TIRKS
Node Locations	Node ID	Text	2	LEIM

## 8.6 DSX

Data Definition	Description	Data Type	Max Char.	Source (Primary, Secondary)
DSX To Equipment	Equipment termination	Text	10	LEIM, TIRKS
Slot Assignment	location			
Configuration (DS1 or	Service Termination Type	Text	4	LEIM, TIRKS
DS3)				

8.7 LGX

				Source (Primary,
Data Definition	Description	Data Type	Max. Char.	Secondary)
Equipment Slot Assignment	Equipment termination location	Text	20	LEIM, FOX
Strand Slot Assignment	Indicates which LGX port corresponds to a fiber strand from an item of equipment	Text	10	LEIM, TIRKS
Capacity	Total possible number of terminations	Text	3	LEIM, FOX

15

8.8 ONU

0	0	N	N A	т	т
<u>۸</u>	. 9	IN	IV	ш	

Data Definition	Description	Data Type	Max Source (Primary, Char. Secondary)	<b>—</b> 20	Data Definition	Description	Data Type	M Cl
PG Count Range	Derived counts assigned	Text	20 LEIM, LFACS	_	Circuit Id	System Circuit Id	Text	2

## 8.10 DLC

Data Definition	Description	Data Type	Max Char.	Source (Primary, Secondary)
Mode	Mode "I" "II" or "III"	Text	3	LEIM
Line Code	"AMI" or "B8ZS"	Text	4	LEIM
System Type	Manufacturer Code	Text	6	LEIM, LFACS
PG Counts (Pair Gain Counts)	Counts assigned to DLE equipment slots to provide LFACS assignment capability	Text	18	LEIM, LFACS
DSX Assignment	DS1 Termination location	Text	4	LEIM

86

Source (Primary, Secondary)

TIRKS

## 8.11 Fiber Splice

Data Definition	Description	Data Type	Max Char.	Source (Primary, Secondary)
Default Splice Type	System determined splice type			
Field Verified Splice	The actual type of splice used			
Type	based on field verification			
System Determined	Default loss associated with			
Loss				
Field Verified Loss	The actual loss based on field verification			
Source	IPID# and complement which is on the CO side of the splice			
Destination	IPID# and complement which is on the field side of the splice			

## 8.12 Switch

Data Definition	Description	Data Type	Max Char.	Source (Primary, Secondary)
System Type	Manufacturer Code DS1 Termination location	Text	6	LEIM
DSX Assignment		Text	4	LEIM

## 8.13 Repeater Shelf

Data Definition	Description	Date Type	Max Char.	Source (Primary, Secondary)
DSX Assignment	DS1 Termination location	Text	6	LEIM, TIRKS
Shelf Assignment (Circuit)	DS1 or DS3 Circuit ID	Text	25	LEIM, TIRKS
Shelf Capacity	Number of slots in a shelf	Text	3	LEIM, TIRKS

## 8.14 Fiber Strand

Data Definition	Description	Date Type		Source (Primary, Secondary)
Designation	Name that uniquely identifies a fiber strand inside a wire center	Text	20	FAS, LEIM, personal notes
Diversity	Diverse, Non-Diverse	Text	1	FAS
Fiber Mode	Size of strand code - single or multi-mode	Text	6	FAS
Continuity Relation	State of one item's connection to another	Graphical	N/A	FAS
Terminating Condition	Strand state of termination or non-termination	Graphical	N/A	FAS, LEIM, TIRKS
Type	Department of ownership - Loop or IOP	Text	4	FAS
Beginning Wire Center Name	Name given to a geographic area served by a central office	Text	20	FAS, LEIM, TIRKS
Terminating Wire Center Name	Name given to a geographic area served by a central office	Text	20	FAS, LEIM, TIRKS
Central Office Location	Street Address of CO	Text + Graphical	30	FAS, LEIM, TIRKS
Central Office ID	CO CLLI Code	Text	25	LEIM, TIRKS
RT Location	Strand address of Remote Terminal and Graphical Location	Text + Graphical	30	FAS, LEIM, TIRKS
Position in ribbon or	Position noted by Strand Color	Text	10	FAS
Wavelength	Wavelengths utilized by strand	Text	10	TIRKS
Sheath Assignment	Sheath attributes associated with the strand	Text	10	FAS
Status	Assignment condition - working, assigned, spare, planned	Text	10	LEIM, TIRKS, personal notes
Dry Fiber Indicator	Indicates whether fiber is a "dry fiber" or not	Text	1	LEIM, TIRKS

## 8.15 Fiber Sheath

Data Definition	Description	Date Type		Source (Primary, Secondary)
Manufacturer	Sheath manufacturer	Text	10	FAS
Fiber Type	Cable Core Design	Text	20	FAS
Fiber Mode	Core Size	Text	6	FAS
Attenuation	Expected attenuation (signal loss) of strand	Text	8	FAS
Sheath Type	Over sheath attributes	Text	20	FAS
Tensile Load	Maximum allowable sheath tension	Text	10	FAS
Cable unit type	Configuration of fibers in sheath tube or ribbon	Text	10	FAS
Fibers per unit	Number of guaranteed fibers in sheath units	Text	3	FAS
Size	Number of Fibers	Numeric	4	FAS
IPID#	Item of plant ID in FAS	Numeric	10	FAS
Mortality Date	Year placed in field	Date	4	FAS
Designation	Type or use of fiber - outside, riser, plenum	Text	10	FAS
Reduced Water Peak (RWP) fiber type	Sheath property for new cables	Text	4	FAS

Data Definition	Description	Date Type		Source (Primary, Secondary)
Length	Sheath length	Numeric	8	FAS; records measurement associated with fiber splice
Environment	Sheath environment as described by FRC	Text	6	FAS
Status	Assignment condition - working, assigned, spare, planned	Text	10	LEIM, TIRKS, Personal Notes

## 8.16 Equipment Location

Data Definition	Description	Date Type	Max Char.	Source (Primary, Secondary)
District Name Address Area # Location # Structure Type	District location resides in	Text	25	LEIM, FAS
	Street Address of location	Text	30	LEIM, FAS
	Code the uniquely identifies address	Text	6	LEIM, FAS
	RT and CLLI#	Text	15	LEIM
	Type of structure to house DLE	Text	8	LEIM, FAS

25

#### 8.17 Conduit

Data Definition	Description	Date Type		Source (Primary, Secondary)
Conduit Run	Group of conduits traversing same route	N/A	N/A	N/A
Conduit Type	Material description of conduit	Text	15	FAS, personal notes
Conduit Location	Graphical location of Conduit run	Graphical	N/A	FAS
Conduit length	End to end length of conduit to the nearest foot	Numeric	8	FAS
Manhole name	Name assigned to manhole	Text	8	FAS
Manhole locations	Graphical location of manhole	Graphical	N/A	FAS
Hand hole name	Name assigned to manhole	Text	5	FAS

#### 9 Use Case Modeling

Purpose: The purpose of this section is to provide a highlevel understanding of core system functionality, both user and machine-driven, for FMT.

Discussion: Use-Case diagramming is a simple modeling technique that illustrates the various entities—human and machine (called "Actors")—that can interact with the proposed system. Use-Case diagrams provide a high-level, graphical summary of embodiments and are also useful during the development phase for defining objects in a system.

- 9.1 Use Case Descriptions
- 9.1.1 Use Case: Login and Password
- 9.1.1.1 Description

This use case describes how a user logs into the system. 55 The user needs a valid username and password, which is created by the system administrator. When the user logs in with the correct username and password, the system recognizes the user and sets their appropriate permissions and preferences. 60

9.1.1.2 Actors
Facility Planners
Engineering Assistants
Transmission Engineers
Construction Technicians
Long Term Planners
OSP Engineers

#### 9.1.1.3 Normal Sequence

Sequence Number	Description
1.	The user double-clicks an icon or a selection from the Windows NT Start Menu and launches the application.
2.	The user enters a CUID (Common User Id) and Password.
3.	The application determines the user's role type (Loop Capacity Manager, Engineering Assistant, etc.) and default District and makes appropriate functionality available.
4.	User enters the system with their default settings

#### 9.1.1.4 Alternative Sequence

The user forgets his/her password or enters the wrong password. The system can prompt the user to reenter the password. If the user has forgotten his/her password, they can have to contact the system administrator to reset password.

- 9.2.2 Use Case: Search/Find, View Graphical Elements
- 9.2.2.1 Description

This use case allows the user to search/find or view graphical elements from within the system. The user can input a

search with/without a wildcard or select from a list what they would like to view. The user may also narrow or refine their search to obtain additional information about the search.

9.2.2.2 Actors
Facility Planners
Engineering Assistants
Transmission Engineers
Construction Technicians
Long Term Planners
OSP Engineers
9.2.2.3 Normal Sequence

Sequence Number	Description
1.	User logs into system (see use case: 9.1.1)
2.	User inputs a fiber name, or a part of a fiber name with a wildcard. The application accepts the query and returns a diagram or tabular data based on user's request of the fiber ring from the originating Central Office.
3.	The user "Zooms In" or "Zooms Out" as needed. The system can display more geographic and infrastructure detail when the users "Zoom In" and less detail when they "Zoom Out."
4.	The user selects a feature and the application returns a pop-up window with detailed information about the feature.
5.	The user selects an "Additional Info" option to drill down for additional data on the feature.
6.	The user can print, change focus to another application on the desktop (ALT-TAB for example), re-query or close the window.

#### 9.2.2.4 Alternate Sequences

The user enters a query based on: equipment type constrained by Central Office (Wire Center), remote terminal 45 (which returns all equipment), fiber sheath, or street address. The returned diagram can support zoom in and zoom out features. If the equipment has data associated with it in more than one external system, the returned data window can show the discrepancies. FIG. 12 suggests the concept.

### 9.2.3 Use Case: Query Network Facility Items

#### 9.2.3.1 Description

This use case allows the user to query network facility items from within the system. The system allows the user to search with multiple parameters and wildcards. The user can also narrow the query and view an item by type, date, etc.

#### 9.2.3.2 Actors

Facility Planners

**Engineering Assistants** 

Transmission Engineers

Construction Technicians

Long Term Planners

**OSP** Engineers

#### 9.2.3.3 Normal Sequence

5	Sequence Number	Description
	1.	User logs in (see use case: 9.1.1)
	2.	On the query screen, the system can
		provide multiple parameters for a
		search. For example, a user may
10		want to view fiber sheath(s) by
10		Manufacturer, Type, and Year Placed.
	3.	The user can be able to further
		narrow the search. For example, a user enters Manufacturer and Year
		Placed as parameters, and FMT displays
		a listing of all sheaths meeting
15		the criteria.
	4.	User selects an individual facility
		item to review its data attributes
	5.	User can select another item or log out

#### 9.2.3.4 Alternative Sequence

The user may misspell a word or leave out part of a word. The system should query for words that are similar to the one entered by the user. If no data exists for the parameters entered, the system should prompt the user to try another search

9.2.4 Use Case: Provide Calculation Tools

#### 9.2.4.1 Description

This use case allows the user to obtain calculations from the system by entering criteria into the system or selecting areas or items to be calculated. The system has calculation tools that it uses in the backend to perform such activities. The user may view the calculation graphically or in a tabular format.

<sup>35</sup> 9.2.4.2 Actors

Facility Planners

**Engineering Assistants** 

Transmission Engineers

Construction Technicians

Long Term Planners

**OSP Engineers** 

9.2.4.3 Normal Sequence

Sequence Number	Description
1. 2.	User logs in (see use case: 9.1.1) On the main screen, the user selects what they want calculated or measured
3.	A user may select points graphically, manually input locations, etc. and the system can use the appropriate tool and display the output for the user
4.	The user may input other variables or criteria to obtain other calculations, etc.
5.	Once the user is done he logs out of the system

## 9.2.4.4 Alternative Sequence

The user may enter a wrong spelling of a word when entering search criteria or select an invalid area on map. The system can prompt the user to try again. The user may want to calculate multiple point distances from the map.

93

9.2.5.1 Use Case: Integrate Fiber Related Data

#### 9.2.5.1 Description

This use case allows the user to obtain data that is stored in external systems or in the system's database. The system pulls data from external system and integrates it to display an output for the user.

9.2.5.2 Actors
Facility Planners
Engineering Assistants
Transmission Engineers
Construction Technicians
Long Term Planners
OSP Engineers
9.2.5.3 Normal Sequence

Sequence Number	Description
1.	User logs in (see use case: 9.1.1)
2.	The system can provide the user with the ability to select in a graphical
	environment or on a query screen, and view results in a tabular format.
3.	On the main screen, the user selects an item on a query screen or
	chooses one from a list or select
4.	one from the items currently visible. The user may input other variables
	or criteria to obtain other more detailed information, etc.
5.	The system obtains the appropriate
	data from external systems and/or its database in the backend and
	displays the output for the user to view.
6.	The user views the data and may do another search or refine the search further.
7.	User logs out when finished.

#### 9.2.5.4 Alternative Sequence

The user may enter a search criterion that is not valid or not recognized by the system. The data may not have been integrated from the external systems into the main system, FMT. 40 The system can then display on screen a message that data entered is not recognized by the system, please try again.

9.2.6 Use Case: Provide Fiber Tools and Reports

#### 9.2.6.1 Description

This use case provides user to use tools and view reports 45 generated by the system. The system contains fiber tools that help the user in determining status, priority, or other information about fiber.

9.2.6.2 Actors
Facility Planners
Engineering Assistants
Transmission Engineers
Construction Technicians
Long Term Planners
OSP Engineers
9.2.6.3 Normal Sequence

Sequence Number	Description
1.	User logs in (see use case: 9.1.1)
2.	On the main screen, the system provides various tools for the user to use.
3.	User selects a tool in order to perform a certain function to a fiber, fiber strand, etc. such as assign

94 -continued

Sequence Number	Description
	reservation status, restoration
4.	priority, fiber strand diversity.  The system assigns the value
	appropriately to the fiber according to
	what the user indicated.
5.	The user also may print out or
	view a report about the fiber, etc.
6.	User logs out when finished.

#### 9.2.6.4 Alternative Sequence

The user may select the wrong tool to assign value to fibers.

The system can allow the user to make changes and can ask the user for a confirmation on the changes made. These changes or additions can vary on user permissions.

9.2.7 Use Case: Create, Read, Update, Delete LRS 9.2.7.1 Description

This use case allows user to go into the planning part of FMT. Users can be able to create, read, update, and delete location relief strategies. The functions they can perform can depend on the privileges and permissions that they have according to the login.

9.2.7.2 Actors
Facility Planners
Engineering Assistants
Long Term Planners
9.2.7.3 Normal Sequence

Sequence Number	Description
1.	User logs in to system (see use case: 9.1.1)
2.	User launches Location Relief Strategy with menu item or toolbar button.
3.	User selects the activity they would like to perform (create, read, update, etc.)
4.	The system opens a LRS or allows user to create a new Location Relief Strategy.
5.	User selects a Central Office or area of interest on the District map and "Zooms In"
6.	The user selects symbols, lines from an object palette and draws the design.
7.	User enters comments in comment fields for each object placed on the diagram.
8.	User saves design and selects a "Publish" or "Private" option. The Publish option can make the design available to other users with access to the planning layer.
9.	User logs off when finished.

### 9.2.7.4 Alternate Sequences

50

The user may choose to delete or update a LRS, but not have permission to do so. The system can display a message that the user does not have permission o do the task selected. The user may add comments about the LRS that can be seen by the creator of the LRS and anyone else who has access.

9.2.8 Use Case: View Cross Box Data for Planning

9.2.8.1 Description

This use case allows user to get information about cross boxes in order to use it for planning purposes. The user can be able to do a search or query on cross boxes by date and attach the output data to the LRS they create. This data can used for Location Relief Strategies.

9.2.8.2 Actors
Facility Planners
Engineering Assistants
Long Term Planners
9.2.8.3 Normal Sequence

Sequence Number	Description
1.	User logs in (see use case: 9.1.1)
2.	On the main screen, the user can select cross box data.
3.	User can enter search date parameters for the system to check cross box fills, etc. for the dates specified.
4.	The system can display in graphical and tabular form the cross box data.
5.	User can have the option to attach this data to the LRS that the user can create. If it is attached to the LRS, then anyone who can view the LRS can be able to view the cross box data.
6.	User does a search for a LRS
7.	User associates LRS with Cross Box data
8.	User logs out when completed.

#### 9.2.8.4 Alternative Sequence

The user may want to attach more than one cross box report. The system can allow the user to attach additional reports for each LRS created.

#### 10 Technical

Purpose: This section defines the scope of the architectural platform and the subset of standards applicable to OPEDS Software development. This section can also reference security and other development standards.

#### 10.1 General

A standards based approach to software development may be designed to promote high data integrity, open systems, improved responsiveness to user functionality changes, enhanced reliability and availability, and security of corporate resources, economic efficiency, and scaleable, distributed systems. This section can define the overall scope of the architectural platform and the subset of standards applicable to OPEDS software development. Included can be an overview of the current OPEDS application and infrastructure 45 architectures. This section can also reference security and other development standards.

#### 10.2 Computing Architecture

Technical Reference 73579 Standards can be used in the design, implementation and management of software modules that form an information network. The industry standards for languages, protocol services, interfaces, computer models, etc. may be used. These standards also form the yardstick by which Commercial Off The Shelf (COTS) or prepackaged software applications are considered for deployment. Other conventional computing architectures may be used.

#### 10.3 Computer Asset Protection Guidelines

The Corporate Security Standards practices may be provided.

#### 10.4 SDLC

System Development Life Cycle is a repeatable, corporateendorsed development methodology that is followed for internally developed systems or major enhancement to an 65 existing system. FIG. 13 depicts the System Development Life Cycle. 96

10.5 Other Standards and Guides

10.5.1 GUI Style Guide

Not applicable.

10.5.2 Capability Maturity Model (CMM)

The CMM is an industry-accepted model for software development processes and was developed by the Software Engineering Institute (SEI) at Carnegie Mellon University.

10.5.3 Metrics

Each application, regardless of the SDLC methodology being followed, may collect primitive metrics to be used as an aid in the effective management and maintenance of software. Primitive metrics are those measures that are applicable to any application, regardless of the hardware or software involved. SLIM (Software Life Cycle Management) and SLIM-Control are the tools used to predict and track project defects. Primitive metrics include but are not limited to the following:

- 1. Size of the project in function points
- 2. Lines of Code, by type
- 3. Time to complete the project (broad measure of staff hours)
  - 4. Number of defects originating in each SDLC phase 10.5.4 Configuration Management

A configuration management tool may be used for control of managed/on-site developed software. IBM's CMVC (Configuration Management Version Control) system is currently (circa 1999) used by OPEDS for all software and documentation to manage versions and configurations. COTS or custom code developed at a supplier's facility must be managed by the supplier's configuration management system.

10.6 Technical Design

10.6.1 Design

OPEDS uses a multi-tier architecture. OPEDS is modular in design to promote reuse of system service components. Business logic is accessible through application services. Application services are independently executable. Application services shall be capable of being independently authorized. OPEDS can be modular in design to allow for the addition of new features (e.g., objects and methods) without a need to alter existing functionality.

10.6.2 Open Systems

The system may be compliant with open system standards. 10.6.3 Open APIs

OPEDS shall use an Open API (or Middleware) to provide connection management to:

Client/presentation layer (e.g., Windows Client, WEB Browser)

Business processing layer

External interfaces

Reporting elements (e.g. COTS reporting tool)

Database elements. This can exclude Database Administrator updates to system-related data, but not user-related data.

10.6.4 Interfaces

Communications with external systems and inter-application data transfers can use standard technology.

10.6.5 PC Client Data Access

CORBA 2.0 (ORBIX) compliant software can be the primary middleware product for accessing data from a Windows-NT based client. ODBC, INET, and/or SQLNet can be a secondary option for limited special use situations.

10.6.6 Portability

The system can be designed so as to provide for platform portability with minimal change (i.e. Windows NT platform to a UNIX platform, or between UNIX platforms.).

25

97

10.6.7 Software Development Tools

For custom developed software, the software development tools can be consistent with a Software Development Tool Approved Products List.

10.6.8 Naming Conventions

For custom developed software, the supplier can use naming and coding conventions that are consistent with standards. 10.6.9 Information Modeling

Any information modeling tools used by external suppliers can be industry standards.

10.6.10 Data

The integrity of any replicated database(s) should be maintained on an as close to real-time basis as feasible. Synchronization of a replicated database may not affect the user.

10.6.11 Data Movement

Data transfer between data stores can use middleware that minimizes the amount of human interaction required to set up and monitor the event. Consistent and reliable data can be available for inquiry in a timely manner. An accurate and reliable log of all data transfers between data stores to support 20 an effective audit trail and ensure data integrity can be fully implemented.

Specific transfer methods can be utilized as follows:

Low volume transfers that do not require automation can utilize ftp.

High volume transfers can utilize Sterling Connect: Direct for inter-company transfers and BUFIT for intra-company transfers.

Database to like database transfers should utilize native transfer modes (i.e. SQLNet).

10.6.12 User Interface Design

Data entry screens should be designed so that users are not required to enter the same data more than once. For example, as an OPEDS user moves from screen to screen (i.e., parentchild screens), OPEDS can automatically retrieve data for 35 fields, which exist in both screens from the previous screen and populate the fields in the current screen. OPEDS shall provide a single sign-on Graphical User Interface (GUI) for end-user access and end-user application administration (i.e., defining activation scripts, modifying tables). The GUI display can be Windows-NT based, consistent in icon usage and color assignment, consistent in placement of buttons and menus, consistent in its look and feel, and consistent in presentation of choices to the user provided via pick lists, pull downs, or pop up menus. The system can perform dynamic 45 validation of all user input.

10.6.13 On-Line Help

OPEDS can provide on-line help.

10.6.14 Security Embodiments

Corporate Security Standards practices, should be met.

10.6.15 User Identification

User identification can be a CUID (Common User ID).

10.6.16 Security Audit

Security audits can be performed in accordance with Corporate Security Standards practices.

10.6.17 Operations

OPEDS can be designed to support high availability. OPEDS shall have the capability to be initialized/terminated by manual input or automated script. Each application service can be documented in the context of appropriate libraries. 60 OPEDS shall retain a log of all activation events. OPEDS can provide the capability for daily removal of all completed activation's from the on-line database and for sending them to an archive (i.e., a non-OLTP database, data warehouse database). OPEDS can be remotely administered. A single point 65 of administration, per domain, shall be provided to manage CUIDs and passwords.

98

10.6.18 Backup and Recovery

All corporate data can be backed up.

10.6.19 Application Management

OPEDS can support application management:

Administration (TA Unicenter)

Performance (BEST1)

Software Distribution (DDS for UNIX, and WinDSS for Windows-NT based clients with later migration to SMS (System Management Services) for Windows-NT based clients)

Database (TA Unicenter)

10.6.20 Error Resolution

10.6.20.1 Client Application/User Errors

OPEDS client software can display error-messages onscreen and provide a meaningful nomenclature for notification and resolution.

10.6.20.2 Technical Errors

A standard process may be used to log error messages within the OPEDS server-side computing environment. The supplier can use this process to log errors and provide a meaningful nomenclature for error messages and their resolution.

10.6.21 Timing Embodiments

The system can be designed to insure presentation layer (i.e. GUI) response times for non-background processes in a range that does not exceed performance thresholds specified in the embodiments documentation as measured from the time of the user keystroke entry to the time of the system response to that entry.

10.6.22 Load Projections

At the completion of the design phase, the supplier can be responsible for projecting the CPU, memory, and DASD (Direct Access Storage Device) embodiments for each system platform (client, application server, database server).

10.6.23 Software Delivery

OPEDS software may have version control. Software received shall include release notes as delineated in the OPEDS Definition of Deliverables and a summary of new features or software fixes since the last version. Received OPEDS software shall include release installation, transition and/or data conversion notes as well as fallback procedures.

10.6.24 Work Center Application Integration Group

The supplier can be responsible for working with the Work Center Application Integration group to provide any and all variables and processes required to configure and administer the system including specifying the necessary environment levels, product levels, component levels, patch levels, etc. upon which their product must operate.

10.7 Current OPEDS Architecture

10.7.1 Overview

OPEDS is a distributed system that can run in more than 30 Telecommunication Company's districts and in a corporate environment. The Process/Data Management layer is provided by the OPEDS project. In general, client-side user interfaces communicate with the OPEDS Process/Data Management layer. Orbix, a commercial product that provides a CORBA-compliant interface to the OPEDS Process/Data management layer, is used for this communication.

In general data retrieval can fall into two categories:

10.7.1.1 External System Data

The OPEDS Process/Data management layer can manage data supplied by External Systems and master data maintained in OPEDS. OPEDS client software has access to External Systems data through an API (Application Programming Interface) provided by OPEDS.

10.7.1.2 OPEDS

Some applications retrieve data directly from OPEDS such as graphics, land and facility attribute data.

10.7.2 Workstation Specifications

The OPEDS clients can, for example, run on PCs that meet 5 the minimum following criteria:

166 Pentium Mhz Processor

32 megabytes of RAM, at minimum (64 megabytes is the norm)

The Outside Plant (OSP) NT Workstation baseload Windows 32-bit API compliant (16 bit applications are NOT permitted)

10.7.3 Server/Database Specifications

Any server-side code can run in the currently deployed OPEDS versions of HP-Unix 11.X and Oracle 8.X. In addition, the code can run in a high-availability environment (i.e., HP's Service Guard). There are two classes of servers:

1) Local Server

Local application servers are UNIX-based HP servers running HP/UX. Software should be developed so as to minimize work when migrating to new OS release levels. Local servers provide database, application and file/print services.

2) Data Center Servers

Two types of data center servers exist for OPEDS: corporate database servers and an archive server. The OPEDS corporate database systems are implemented on a UNIX operating system and deployed on an HP hardware platform. These data center servers can be the central database repositories. Data Stores Oracle has been chosen as the primary relational data store for OPEDS data.

10.7.4 System Diagram

FIG. 14 depicts the three-tier architecture with external systems.

10.8 Computing Architecture

10.8.1 OPEDS Data Repositories

OPEDS currently has two repositories for land and facility data:

10.8.1.1 Landbase

The landbase data model is mastered in ESRI's (Environmental Systems Research Institute, Inc.) SDE (Spatial Data 40 Engine) format. The landbase model also stores redundant graphical facility data mastered in facilities (see below). Specifications of the landbase model are available upon request.

10.8.1.2 Facilities

The OPEDS facilities data model comprises data in Oracle, as well as graphical files on a central server. The graphics files are in Microstation .DGN format. Facilities graphics information for a given area is stored in a .DGN file; corresponding land information is stored in a .LND file.

Specifications of the Facilities model are available upon request.

10.8.2 Network Information Services

NIS is used to provide consistency and synchronization of UNIX system files across a homogeneous environment. The 55 NIS domains are unique per district server environment with the Job Management Server acting as the NIS domain master server and all of the other district UNIX servers acting as secondary or slave NIS servers.

10.8.3 Domain Name System (DNS)

The Domain Name System (DNS) is a distributed database that runs on Regional Data Center UNIX hosts, providing a hierarchical naming system for identifying hosts on BOSIP (Open Systems Interconnect Platform). The key embodiment for OPEDS applications is to use DNS to resolve host names 65 stored in OPEDS configuration files. OPEDS applications cannot store IP addresses in configuration files and can only

100

store host names. This can facilitate redirecting clients to alternate servers in failure situations. NetManage TCP/IP software can be configured to utilize DNS to support OPEDS node name resolution.

10.8.4 OPEDS Process/Data Management Layer

The OPEDS Process/Data Management Layer provides access to data located on various application and data servers. This service can provide contract and messaging API(s) to directly access legacy data systems where available and provide access to intermediate service providers to legacy systems as well. These service providers can provide a variety of services including terminal emulation access to legacy 3270-based systems.

10.8.5 Wide Area Network

The Outside Plant networking environment consists of LANs interconnected to form a Wide Area Network (WAN) via BOSIP. In addition, access is provided to the Virtual Circuit Switch Network (VCSN). The goal is to provide the users with transparent and reliable access to all essential OSP systems as well as to legacy systems.

In the OPEDS architecture, BOSIP is the backbone upon which the majority of data communication relies. BOSIP is a Transmission Control Protocol/Internet Protocol (TCP/IP) based network, which fully supports distributed computing as outlined in the BSCA strategy. The design goal is to provide universal communication services independent of the underlying physical network. OPEDS utilizes the TCP/IP protocol.

10.8.6 External System Data

The OPEDS Process/Data management layer can manage data supplied by External Systems and master data maintained in OPEDS. OPEDS clients have access to the External Systems data through an API (Application Programming Interface) provided by OPEDS.

10.9 OPEDS Topology

FIG. 15 depicts an OPEDS topology.

10.9.1 Data Center

A data center is shown in FIG. 16.

The OPEDS Corporate Data Stores for facilities and land are located in the Charlotte Data Center. The archive server and storage are located in the Data Center as well. OSPCM and legacy systems are located in all production data centers.

10.9.2 Typical District/RLAC

FIG. 17 depicts a District/RLAC.

11 Reference Items

60

11.1 Glossary of Terms for the FMT and Systems

Asynchronous Digital Subscriber Line Description: Digital communications services available over twisted pair copper Assignment Description: Data generally associated with the location of fiber terminations, and the MUXs the fibers are traveling through CO Central Office Description: Central location where all facilities inside a wire center terminate. Common User ID The 7-character unique user id for Description: all FMT Users. DLE Digital Loop Electronics

101 102 continued -continued

-continued		
	-continued	_
Description:	Digital transmission equipment used	
	to generate DSO, DS1 and DS3 signals etc.	_
EWO	Engineering Work Order	5
Description:	OSP authorization to perform construction work activity.	
FITL	Fiber in the Loop	
Description:	Communication platform that uses fiber to deliver services to the	
	customer's curb.	10
FMT	Fiber Management Tool	
Description:	The proposed module of OPEDS that is the focus of this document.	
FOX	The Fiber Optic Xconnect system	
Description:	A system used by Inter-Office planners to track of Multiplexer (MUX)/LGX	1.5
	assignments.	15
HW	Hardwired	
Description: IOF	DLE equipment in place, but not active InterOffice Planner	
Description:	Planner responsible for planning and	
	administering facilities between	20
IP	Central Offices. Long Term Planner	
Description:	Planner that performs high-level	
IPID	district fiber optic route planning.  Item of Plant Identification	
Description:	Capitalized material identification	
	number.	25
LATA Description:	Local Access Toll Area Local calling area controlled by	
Description.	local access provider.	
FACILITY	Loop Capacity Manager	
PLANNERS Description:	Planner Responsible for non-Central	30
Description.	Office locations and facilities.	
LEIM	The Loop Equipment Inventory Module	
Description:	The corporate repository of OSP	
LFACS	Digital Loop Electronic data. The Loop Facility Assignment Control	
	System	35
Description:	The system used to monitor and	
	assign facilities. The system monitors the copper network, but	
	also has fiber and equipment	
	information. LFACS stores fiber	40
	assignment information for some, but not all, Wire Centers. The	
	data in LFACS mirrors the data in	
	LEIM.	
LGX Description:	Light Guide Cross Connect Termination equipment for fiber	
Description.	optic cables and jumpers.	45
LMU	Loop Make Up	
Description:	Loop distance and cable character-	
	istics associated with a specific cable pair.	
MUX	Multiplexer	50
Description:	DLE equipment used to aggregate	
NMLI	or segregate digital signals.  Native Mode LAN Interconnection	
Description:	MUX and fiber connections between	
	LANS	
ONU Descriptions	Optical Node Unit	55
Description:	OSP termination point for FITL distribution fiber at the customer's	
	location.	
OPEDS	Outside Plant Engineering Design	
Description:	System A system Outside Plant facilities	60
2 compaon	and landbase.	
OSP	Outside Plant Engineer	
Description:	Engineers responsible for all facilities not in a Central Office.	
OTDR	Optical Time Domain Reflectometer	
Dogovintion	Equipment used to test fiber	65

Equipment used to test fiber

spans with an optical test.

Description:

	PG	Pair Gain
5	Description:	Designation assigned to DS0
		counts derived by DLE.
	RSDC	Regional Design Source Code
	Description:	Code used to order DLE equipment
		via OSPCM (Outside Plant
		Construction Management System)
		instead of TEO.
	ROW	Right of Way
10	Description:	Municipal-owned property associated
		with public infrastructure.
	RT	Remote Terminal
	Description:	DLE location outside of a central
	aom	office.
	SCID	Sonet Circuit Identification
15	Description:	Unique identification given to
	CONTE	SONET systems.
	SONET	Synchronous Optical Network
	Description:	A type of fiber optic network
		that requires the two endpoints to
20	TEO	synchronize data transmission.
		Telephone Equipment Order Form used to order DLE from
	Description:	
	TIRKS	outside company. Trunks Inventory Record Keeping
	TIKKS	System
	Description:	The corporate repository of
	Description.	InterOffice digital equipment
25		and digital circuits.
		and argum onomis.

12 Further Details with Respect to Methods, Systems and Computer Program Products for Planning Resources Based on Primary and Alternate Location Relief Strategies

FMTs and systems for planning resources based on location relief strategies have been described above in accordance with some embodiments of the present invention. This section more generally describes the methods, systems and computer program products for planning resources based on primary and alternate location relief strategies according to some other embodiments of the present invention.

FIG. 18 is a block diagram of a resource planning system 100 and associated methods and computer program products in accordance with some embodiments of the present invention. The data processing system 100 typically includes input device(s) 132 such as a keyboard or keypad, a display 134, and a memory 136 that communicate with a processor 138 via an address/data bus 148. The processor 138 can be any commercially available or custom microprocessor. The data processing system 100 may further include a speaker 144 and I/O data ports 146 that also communicate with the processor 138. The I/O data ports 146 can be used to transfer information between the data processing system 100 and another computer system and/or a network. These components may be conventional components, such as those used in many conventional data processing systems, which may be configured to operate as described herein.

The memory 136 is representative of the overall hierarchy of memory devices containing the software and data used to implement the functionality of the resource planning system 100. As shown in FIG. 18, the memory 136 may include several categories of software and data used in the resource planning system 100: an operating system 152; application programs 154; input/output (I/O) device drivers 158; and data 156. As will be appreciated by those of skill in the art, the operating system 152 may be any operating system suitable for use with a resource planning system, such as OS/2, AIX, System390 or Z/OS from International Business Machines Corporation, Armonk, N.Y., Windows95, Windows98, Windows2000 or WindowsXP from Microsoft Corporation, Red-

mond, Wash., Unix or Linux. The I/O device drivers 158

typically include software routines accessed through the operating system 152 by the application programs 154 to communicate with devices such as the I/O data port(s) 146 and certain memory 136 components. The application programs 154 are illustrative of the programs that implement the 5 various features of the resource planning system 100 and preferably include at least one application which supports operations according to embodiments of the present invention. Finally, the data 156 represents the static and dynamic data used by the application programs 154, the operating 10 system 152, the I/O device drivers 158, and other software programs that may reside in the memory 136.

As is further seen in FIG. 18, the data 156 can include data sets that define resources 160, geographic information 162, and location relief strategy plans 164, and that may also 15 define resource needs data sets 166. The geographic information data 162 may define roads, buildings, and/or topographical information, such as was discussed above. The resource data 160 may define the location, type, number, performance, cost, availability and/or other characteristics of resources, such as was discussed above. The defined resources may include, but not be limited to, central offices and fiber optic and electrical communication lines. The resource data 160 may define where resources are presently located relative to the geographic information data.

The resource needs data sets 166 may define one or more resource capacity needs that are associated with geographic locations. For example, one of the resource needs data sets 166 may define a number of communication lines and/or communication bandwidth that is presently needed or pro- 30 jected to be needed at a defined geographic location. The term "location" as used herein can include a defined geographic point, such as a mail address or latitude and longitude coordinates, and can also include a geographic area. The LRS plan data sets 164 may define one or more LRS plans that are 35 associated with each of the resource needs data sets 166. For example, one of the LRS plan data sets 164 may define a number of resources, such as resources for carrying telecommunications (e.g., fiber optic communication lines and/or electrical communication lines), gas lines, water lines, cable 40 television lines, and/or electrical lines, that may be installed and/or retired at a geographic location on a defined date in an attempt to satisfy the resource needs defined by one of the resource needs data sets 166.

More than one of the LRS plan data sets 164 may be 45 associated with one of the resource needs data sets 166. When more than one of the LRS plan data sets 164 are associated with one of the resource needs data sets 166, one of them may be defined as a primary LRS plan and the others may be defined as an alternate LRS plan. The primary LRS plan may 50 correspond to what a Long Term Planner perceives as a preferred way of satisfying the associated resource need, while the alternate LRS plans may correspond to what are perceived as less preferred ways. Accordingly, a preferred LRS plan and one or more alternate LRS plans may be defined in the LRS 55 plan data sets 164 and associated with each resource need defined in the resource needs data sets 166. Such association of preferred LRS plan and alternate LRS plans with a resource need may allow a Long Term Planner to define many different resource plans for meeting a resource need, and to designate 60 a preferred resource plan while maintaining the other LRS plans for further use (e.g., documentation and/or analysis).

The application programs **154** can include a resource planning application **170**, which may include a database **172**. Although the database application **172** is illustrated as part of 65 the resource planning application **170**, for purposes of illustration only, in some other embodiments of the present inventional programs **154** can include a resource planning application **170**, for purposes of illustration only, in some other embodiments of the present inventional programs **154** can include a resource planning application **170**, which may include a resource planning application **170**, which may include a resource planning application **170**, which may include a database **172**.

104

tion the functionality of the database application 172 may be at least partially outside the resource planning application 172. The database application 172 may be any conventional database application that performs conventional data functions such as, for example, Oracle, Microsoft Access, or a custom database application. The resource planning application 170 can import data sets, including existing resource, geographic data, LRS plans, and/or resource needs, from the data portion 156 of the memory 136 into the database 172.

The resource planning application 170 can be one or more GIS tools that can allow a planner to define and associate resources with geographic features in digitized maps. The resource planning application  $170\,\mathrm{may}$  allow a user to at least partially define and/or evaluate the resources 160, the geographic information 162, the resource needs 166, and/or the location relief strategy plan 164. For example, the resource planning application 170 may allow a user to associate one more LRS plans 164 with one of the resource needs 166, and to define which of the associated LRS plans 164 is a primary LRS plan and/or which are alternate LRS plans. When a plurality of the LRS plans are associated with a resource need, the LRS plans may be prioritized (e.g., ranked). A highest priority one of the LRS plans may then be defined as a primary LRS plan, and the other LRS plan(s) may be defined as alternate LRS plans. In some embodiments of the present invention, only one of the LRS plans 164 that are associated with one of the resource needs 166 can be defined as a primary LRS plan.

The resource planning application 170 also generates a resource plan based on the primary LRS plan and/or the alternate LRS plan. The generated resource plan may be generated by, for example, displaying on the display 134 the resources that presently exist in a defined geographical area, as defined by the resource data sets 160, and the primary LRS plan and/or alternate LRS plan. The displayed resources and plans may be overlaid on a map formed by a relevant potion of the geographical information data 162. A resource planner or other user may use the input devices 132 to select which of the LRS plans 164 are included in the resource plan. For example, a resource plan may be generated based on the primary LRS plans, or it may be generated based on selected ones of the primary LRS plans and/or alternate LRS plans. A user may also define access privileges for the LRS plans, such as public or private, which may be used by the resource planning application 170 to limit access of one or more of the LRS plans to users who satisfy the defined access privileges.

The resource planning application 170 may generate a resource plan that combines all or selected ones of the primary LRS plans and/or alternate LRS plans for more than one of the defined resource needs 166, and/or the resource planning application 170 may generate a different resource plan for each of the defined resource needs 166.

Reference is now made to FIG. 19, which illustrates existing resources and two resource needs 220 and 230 as they may be displayed by a resource planning system according to some embodiments of the present invention. The existing resources include two central offices (COs) 202 and 204 and electrical communication lines 210a-j that are communicatively connected to the central offices 202 and 204. Each of the electrical communication lines 210a-j include defined characteristics that include a reference number (i.e., 2XXX), a planned installation date (i.e., 2004 or 2005), the number of copper pairs in the line, the gauge (i.e., thickness) of the copper pairs, and the connections between, and relative locations, of the lines 210a-j and the central offices 202 and 204. Each of the resource needs 220 and 230 have been defined for a geographic position relative to the existing resources. A

user, such as a resource planner, may then use the resource planning system to define and compare LRS plans that may satisfy the defined resource needs 220 and 230.

An example resource plan 300 is illustrated in FIG. 20 that combines the existing resources and defined primary and 5 alternate LRS plans responsive to the resource needs 220 and 230. One primary LRS plan 310 has been defined and associated with the resource need 220. One primary LRS plan 320 and two alternate LRS plans 330 and 340, which are proposed alternative plans, have been defined and associated with the other resource need 230. The primary LRS plan 310 defines a planned connection from the communication line 210f to the resource need 220 in the year 2005. The primary LRS plan 320 defines a planned connection from the central office 204 to the resource need 230 in the year 2004. The alternative LRS plan 330 defines a connection from the communication line 210h to the resource need 230 in the year 2005, and the other alternative LRS plan 340 defines a connection from the communication line 210b to the resource need 230 in the year

According to some embodiments of the present invention, a user may select which of the primary and/or alternate LRS plans are to be displayed with the existing resources. For example, with reference to FIG. 21, the resource plan 300 has been illustrated with the primary LRS plans 310 and 320 25 shown, and the alternative LRS plans 330 and 340 (FIG. 20) hidden. Accordingly, a user may view only the primary LRS plans and hide any alternate plans. A user may similarly filter what information in a resource plan is displayed based on attributes that are associated with the LRS plans, such as 30 when LRS plans are expected to be completed, whether resources associated with LRS plans are direct buried (e.g., buried in the ground without a conduit), buried within a conduit, and/or suspended on a utility pole. A user may thereby selectively view what resources can be available by a 35 particular date and/or based on other attributes that are associated with the resources. The resource plan(s) may be overlaid on geographic information, such as the geographic maps that are illustrated and described above.

A resource management system may alternatively, or addi- 40 tionally, generate reports on existing and/or planned resources relative to dates and/or needs. The resource management system may also summarize the individual and/or combined characteristics of the existing and/or planned resources, including location, type, number, performance, 45 on a resource need, the method comprising: cost, availability and/or other characteristics of resources, such as those discussed above.

A user may thereby define and/or evaluate in the resource planning system one or more resource needs, and may then define and/or compare one or more LRS plans that may be 50 used to address the resource needs. A user may also change the designation of a LRS plan, such as from primary to alternate or vice-versa. More than one LRS plan may be associated with a resource, and the LRS plans may be relatively defined as primary and alternate plans. By maintaining the alternative 55 LRS plans associated with a resource need, in addition to the primary LRS plans, the resource planning system may document for later use why a particular LRS plan was selected.

Although the resource planning application 170, the database 172, and the components of the data 156 of memory 136 60 are illustrated in FIG. 18 as being part of a single resource planning system 100, as will be appreciated by those of skill in the art, the illustrated functionality and data may be distributed across one or more resource planning systems. For example, the functionality of the database 172 and the 65 resource data 160 and geographic information data 162 may be provided on one or more resource planning systems that

106

are separate from the resource planning system that provides the functionality of the resource planning application 170, the local relief strategy plan data 164, and/or resource needs data 166. It will also be appreciated that various applications could be incorporated into some other logical division of the resource planning system 100. Thus, the present invention should not be construed as limited to the configuration of FIG. 18, but is intended to encompass any arrangement, division of functions between resource planning systems and/or configuration capable of carrying out the operations described herein.

Reference is now made to FIG. 22 which illustrates a flowchart of operations that may be used to planning resource according to various embodiments of the present invention. At Block 400, existing resource that are associated with a defined geographic location are imported into the resource management application. At Block 410, geographic information that is associated with a defined geographic location is imported into the resource management application. At Block 420, resources needs are defined. At Block 430, LRS plans 20 that are defined and associated with a resource need and/or are imported into the resource management application. At Block **440**, one of the LRS plans is defined as a primary LRS plan, and, at Block 450, other ones of the LRS plans are defined as alternate LRS plans. As will be appreciated, the defined/ imported LRS plans may be defined by a default alternate/ primary designation so that a user may only need to change the default designation(s) for the defined/imported LRS plans so as distinguish the primary LRS plan from the alternate LRS plans. Accordingly, Block 440 or Block 450 may thereby be eliminated in some embodiments of the present invention. At Block 460, a user may select which LRS plans that are and/or are not to be displayed. At Block 470, the LRS plans may be displayed with the resource need(s), the existing resources and/or the geographic information to a user. The operations 440-470 can be referred to by the dashed Block 435 as exemplary operations for generating a resource plan according to various embodiments of the present invention.

In the drawings and specification, there have been disclosed exemplary embodiments of the invention. Although specific terms are employed, they are used in a generic and descriptive sense only and not for purposes of limitation, the scope of the invention being defined by the following claims.

That which is claimed is:

1. A computer-based method of planning resources based

performing operations as follows on a processor;

importing into a resource planning application that executes on a resource planning system a plurality of location relief strategy plan data sets for installing and retiring apparatus resources in a defined geographic region, wherein one of the location relief strategy plan data sets is defined as a primary location relief strategy plan for installing and retiring apparatus resources in the defined geographic region and one other one of the location relief strategy plan data sets is defined as an alternate location relief strategy plan for installing and retiring apparatus resources in the defined geographic region, and the primary location relief strategy plan and the alternate location relief strategy plans are maintained in a memory of the resource planning system;

generating within the resource planning application a resource plan based on the primary location relief strategy plan and the alternate location relief strategy plan;

displaying on a display device a graphical representation of the primary location relief strategy plan overlaid on a geographic map of the defined region without displaying a graphical representation of the alternative location

relief strategy plan in response to receiving a first user input and displaying on the display device a combination of a graphical representation of the primary location relief strategy plan and a graphical representation of the alternative location relief strategy plan overlaid on the 5 geographic map of the defined region in response to receiving a different second user input; and

initiating installation, retirement, and repair of one of the apparatus resources based on the resource plan;

wherein the apparatus resources comprise part of a net- 10 work infrastructure that is to provide services for multiple entities; and

wherein initiating repair of one of the apparatus resources comprises determining a location of damage to a fiber optic asset based on the resource plan and optical time- 15 domain reflectormeter information.

2. The method of claim 1, further comprising: prioritizing the location relief strategy plan data sets; selecting the highest priority location relief strategy plan data set as the primary location relief strategy plan; and 20 designating the one other of the location relief strategy plan data sets as the alternate location relief strategy plan.

3. The method of claim 1, further comprising:

changing the location relief strategy plan data set that is defined as a primary location relief strategy plan to be 25 defined as an alternate location relief strategy plan; and

changing one of the other location relief strategy plan data sets that is defined as an alternate location relief strategy plan to be defined as a primary location relief strategy

- **4**. The method of claim **1**, wherein generating a resource plan based on the primary location relief strategy plan and the alternate location relief strategy plan comprises selectively displaying one of the primary location relief strategy plan or and the alternate location relief strategy plan based on an 35 input selection from a user.
  - **5**. The method of claim **1**, further comprising:

importing into the resource planning application a plurality of location relief strategy plan data sets that are associated with a plurality of resource needs, wherein only one 40 of the location relief strategy plan data sets associated with each of the resource needs is defined as the primary location relief strategy plan; and

generating within the resource planning application a resource plan for each of the resource needs based on the 45 associated primary location relief strategy plan and the associated alternate location relief strategy plan.

- 6. The method of claim 5, wherein a plurality of the location relief strategy plan data sets associated with one of the resource needs are defined as alternate location relief strategy 50
- 7. The method of claim 5, wherein generating a resource plan for each of the resource needs comprises generating each of the resource plans based only on user selected ones of the associated location relief strategy plan data sets.
- 8. The method of claim 5, wherein generating a resource plan for each of the resource needs comprises generating each of the resource plans based only on the associated primary location relief strategy plans.
- 9. The method of claim 5, wherein generating a resource 60 plan for each of the resource needs comprises generating each of the resource plans based on the associated primary location relief strategy plan and user selected ones of the associated alternate location relief strategy plans.
  - 10. The method of claim 1, further comprising: toggling back and forth between the displaying of the graphical representation of the primary location relief

108

strategy plan and the displaying the combination of the graphical representation of the primary location relief strategy plan and the alternative location relief strategy plan responsive to alternating first and second user inputs.

11. The method of claim 1, further comprising:

displaying, on the display device as an overlay on the geographic map of the defined region, the graphical representation of the primary location relief strategy plan for installing and retiring apparatus resources for carrying telecommunications in the defined geographic region without displaying a graphical representation of the alternative location relief strategy plan in response to a first user input;

displaying, on the display device as an overlay on the geographic map of the defined region, a combination of a graphical representation of the primary location relief strategy plan for installing and the retiring apparatus resources in the defined geographic region and a graphical representation of the alternative location relief strategy plan for installing and retiring the apparatus resources for carrying telecommunications in the defined geographic region in response to a different second user input; and

toggling back and forth between the displaying of the graphical representation of the primary location relief strategy plan and the displaying the combination of the graphical representation of the primary location relief strategy plan and the alternative location relief strategy plan responsive to alternating first and second user inputs.

12. The method of claim 11, further comprising:

displaying, on the display device as an overlay on the geographic map of the defined region, the graphical representation of the primary location relief strategy plan for installing and retiring a number of fiber optic communication lines and electrical communication lines in the defined geographic region without displaying a graphical representation of the alternative location relief strategy plan in response to a first user input;

displaying, on the display device as an overlay on the geographic map of the defined region, a combination of a graphical representation of the primary location relief strategy plan for installing and retiring the number of fiber optic communication lines and electrical communication lines in the defined geographic region and a graphical representation of the alternative location relief strategy plan for installing and retiring the apparatus resources for carrying telecommunications in the defined geographic region in response to a different second user input; and

toggling back and forth between the displaying of the graphical representation of the primary location relief strategy plan and the displaying the combination of the graphical representation of the primary location relief strategy plan and the alternative location relief strategy plan responsive to alternating first and second user inputs.

13. The method of claim 1, further comprising:

displaying, on the display device as an overlay on the geographic map of the defined region, the graphical representation of the primary location relief strategy plan for installing and retiring a number of gas lines, electrical lines, and water lines in the defined geographic region without displaying a graphical representation of the alternative location relief strategy plan in response to a first user input;

displaying, on the display device as an overlay on the geographic map of the defined region, a combination of a graphical representation of the primary location relief strategy plan for installing the number of gas lines, electrical lines, and water lines in the defined geographic region and a graphical representation of the alternative location relief strategy plan for installing and retiring apparatus resources for carrying telecommunications in the defined geographic region in response to a different second user input; and

toggling back and forth between the displaying of the graphical representation of the primary location relief strategy plan and the displaying the combination of the graphical representation of the primary location relief strategy plan and the alternative location relief strategy plan responsive to alternating first and second user inputs

14. The method of claim 1, wherein the primary location relief strategy plan and the alternate location relief strategy 20 plan each correspond to a plan for installing and retiring cable television lines at a geographic location.

15. A resource planning system comprising:

a computer processor; and

a non-transitory memory comprising computer readable <sup>25</sup> program code that when executed by the computer processor causes the computer processor to perform operations comprising:

importing into a resource planning application that executes on the computer processor a plurality of location relief strategy plan data sets for installing and retiring apparatus resources in a defined geographic region, wherein one of the location relief strategy plan data sets is defined as a primary location relief strategy plan for installing and retiring apparatus resources in the defined geographic region and one other one of the location relief strategy plan data sets is defined as an alternate location relief strategy plan for installing and retiring apparatus resources in the defined geographic region, and the primary location relief strategy plan and the alternate location relief strategy plans are maintained in the memory;

generating within the resource planning application a resource plan based on the primary location relief strategy plan and the alternate location relief strategy plan;

displaying on a display device a graphical representation of the primary location relief strategy plan overlaid on a geographic map of the defined region without displaying a graphical representation of the alternative location relief strategy plan in response to receiving a first user input and displaying on the display device a combination of a graphical representation of the primary location relief strategy plan and a graphical representation of the alternative location relief strategy plan overlaid on the geographic map of the defined region in response to receiving a different second user input; and

initiating installation, retirement, and repair of one of the apparatus resources based on the resource plan;

60

wherein the apparatus resources comprise part of a network infrastructure that is to provide services for multiple entities; and

wherein initiating repair of one of the apparatus resources comprises determining a location of damage to a fiber 65 optic asset based on the resource plan and optical timedomain reflector information. 110

16. The resource planning system of claim 15, wherein the operations further comprise:

importing into the resource planning application a plurality of location relief strategy plan data sets that are associated with a plurality of resource needs, wherein only one of the location relief strategy plan data sets associated with each of the resource needs is defined as a primary location relief strategy plan and a plurality of the location relief strategy plan data sets associated with some of the resource needs are defined as alternate location relief strategy plans; and

generating within the resource planning application a resource plan for each of the resource needs by displaying, via the display, the primary location relief strategy plan and the alternate location relief strategy plans based on a user selection signal.

17. The resource planning system of claim 16, wherein the operations further comprise:

generating through the resource planning application a resource plan for each of the resource needs by displaying the primary location relief strategy plan and selectively displaying the alternate location relief strategy plans based on the user selection signal.

18. A computer program product for planning resources based on a resource need, the computer program product comprising program code embodied in a non-transitory computer-readable storage medium that when executed by a computer processor causes the processor to perform operations comprising:

importing into a resource planning application that executes on the computer processor a plurality of location relief strategy plan data sets for installing and retiring apparatus resources in a defined geographic region, wherein one of the location relief strategy plan data sets is defined as a primary location relief strategy plan for installing and retiring apparatus resources in the defined geographic region and one other one of the location relief strategy plan data sets is defined as an alternate location relief strategy plan for installing and retiring apparatus resources in the defined geographic region, and the primary location relief strategy plan and the alternate location relief strategy plans are maintained in a memory of the resource planning system;

generating within the resource planning application a resource plan based on the primary location relief strategy plan and the alternate location relief strategy plan;

displaying on a display device a graphical representation of the primary location relief strategy plan overlaid on a geographic map of the defined region without displaying a graphical representation of the alternative location relief strategy plan in response to receiving a first user input and displaying on the display device a combination of a graphical representation of the primary location relief strategy plan and a graphical representation of the alternative location relief strategy plan overlaid on the geographic map of the defined region in response to receiving a different second user input; and

initiating installation, retirement, and repair of one of the apparatus resources based on the resource plan;

wherein the apparatus resources comprise part of a network infrastructure that is to provide services for multiple entities; and

wherein initiating repair of one of the apparatus resources comprises determining a location of damage to a fiber optic asset based on the resource plan and optical timedomain reflectometer information.

19. The computer program product according to claim 18, wherein a plurality of the location relief strategy plan data sets that are associated with the resource need are defined as alternate location relief strategy plans, and the operations further comprise:

displaying one of the location relief strategy plans among the primary location relief strategy plan and the plurality of alternate location relief strategy plans that are associated with the resource need based on a user selection.

\* \* \* \* \*

## UNITED STATES PATENT AND TRADEMARK OFFICE

## **CERTIFICATE OF CORRECTION**

PATENT NO. : 9,245,241 B2 Page 1 of 1

APPLICATION NO. : 10/885191
DATED : January 26, 2016
INVENTOR(S) : Mansfield et al.

It is certified that error appears in the above-identified patent and that said Letters Patent is hereby corrected as shown below:

## In the Claims:

Column 107, Claim 4, Lines 34 - 35: Please correct "plan or and the" to read -- plan and the --

Signed and Sealed this Twenty-sixth Day of April, 2016

Michelle K. Lee

Michelle K. Lee

Director of the United States Patent and Trademark Office